ETSITS 132 442 V19.0.0 (2025-10)



Digital cellular telecommunications system (Phase 2+) (GSM); Universal Mobile Telecommunications System (UMTS); LTE;

Telecommunication management;
Trace Management Integration Reference Point (IRP);
Information Service (IS)
(3GPP TS 32.442 version 19.0.0 Release 19)



Reference RTS/TSGS-0532442vj00 Keywords GSM,LTE,UMTS

ETSI

650 Route des Lucioles F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - APE 7112B Association à but non lucratif enregistrée à la Sous-Préfecture de Grasse (06) N° w061004871

Important notice

The present document can be downloaded from the ETSI Search & Browse Standards application.

The present document may be made available in electronic versions and/or in print. The content of any electronic and/or print versions of the present document shall not be modified without the prior written authorization of ETSI. In case of any existing or perceived difference in contents between such versions and/or in print, the prevailing version of an ETSI deliverable is the one made publicly available in PDF format on ETSI deliver repository.

Users should be aware that the present document may be revised or have its status changed, this information is available in the Milestones listing.

If you find errors in the present document, please send your comments to the relevant service listed under <u>Committee Support Staff</u>.

If you find a security vulnerability in the present document, please report it through our Coordinated Vulnerability Disclosure (CVD) program.

Notice of disclaimer & limitation of liability

The information provided in the present deliverable is directed solely to professionals who have the appropriate degree of experience to understand and interpret its content in accordance with generally accepted engineering or other professional standard and applicable regulations.

No recommendation as to products and services or vendors is made or should be implied.

No representation or warranty is made that this deliverable is technically accurate or sufficient or conforms to any law and/or governmental rule and/or regulation and further, no representation or warranty is made of merchantability or fitness for any particular purpose or against infringement of intellectual property rights.

In no event shall ETSI be held liable for loss of profits or any other incidental or consequential damages.

Any software contained in this deliverable is provided "AS IS" with no warranties, express or implied, including but not limited to, the warranties of merchantability, fitness for a particular purpose and non-infringement of intellectual property rights and ETSI shall not be held liable in any event for any damages whatsoever (including, without limitation, damages for loss of profits, business interruption, loss of information, or any other pecuniary loss) arising out of or related to the use of or inability to use the software.

Copyright Notification

No part may be reproduced or utilized in any form or by any means, electronic or mechanical, including photocopying and microfilm except as authorized by written permission of ETSI.

The content of the PDF version shall not be modified without the written authorization of ETSI.

The copyright and the foregoing restriction extend to reproduction in all media.

© ETSI 2025. All rights reserved.

Intellectual Property Rights

Essential patents

IPRs essential or potentially essential to normative deliverables may have been declared to ETSI. The declarations pertaining to these essential IPRs, if any, are publicly available for ETSI members and non-members, and can be found in ETSI SR 000 314: "Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards", which is available from the ETSI Secretariat. Latest updates are available on the ETSI IPR online database.

Pursuant to the ETSI Directives including the ETSI IPR Policy, no investigation regarding the essentiality of IPRs, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

Trademarks

The present document may include trademarks and/or tradenames which are asserted and/or registered by their owners. ETSI claims no ownership of these except for any which are indicated as being the property of ETSI, and conveys no right to use or reproduce any trademark and/or tradename. Mention of those trademarks in the present document does not constitute an endorsement by ETSI of products, services or organizations associated with those trademarks.

DECTTM, **PLUGTESTS**TM, **UMTS**TM and the ETSI logo are trademarks of ETSI registered for the benefit of its Members. **3GPP**TM, **LTE**TM and **5G**TM logo are trademarks of ETSI registered for the benefit of its Members and of the 3GPP Organizational Partners. **oneM2M**TM logo is a trademark of ETSI registered for the benefit of its Members and of the oneM2M Partners. **GSM**[®] and the GSM logo are trademarks registered and owned by the GSM Association.

Legal Notice

This Technical Specification (TS) has been produced by ETSI 3rd Generation Partnership Project (3GPP).

The present document may refer to technical specifications or reports using their 3GPP identities. These shall be interpreted as being references to the corresponding ETSI deliverables.

The cross reference between 3GPP and ETSI identities can be found at 3GPP to ETSI numbering cross-referencing.

Modal verbs terminology

In the present document "shall", "shall not", "should", "should not", "may", "need not", "will", "will not", "can" and "cannot" are to be interpreted as described in clause 3.2 of the <u>ETSI Drafting Rules</u> (Verbal forms for the expression of provisions).

"must" and "must not" are NOT allowed in ETSI deliverables except when used in direct citation.

Contents

Intelle	ectual Property Rights	2
Legal	Notice	2
Moda	l verbs terminology	2
Forew	vord	5
Introd	luction	5
1	Scope	
2	References	
3	Definitions and abbreviations.	
3.1	Definitions and aboreviations.	
3.2	Abbreviations	
4	System Overview	
-	System context	
4.1 4.2	Compliance rules	
	•	
5	Information Object Classes	
5.1	Imported information entities and local labels	
5.2	Class diagram	
5.2.1	Attributes and relationships	
5.2.2	Inheritance	
5.3	Information object class definitions	
5.3.1	TraceJob	
5.3.1.1		
5.3.1.2		
5.3.1.3		
5.3.2 5.2.2.1	TraceRecord	
5.3.2.1		
5.3.2.2		
5.3.3 5.3.3.1	TraceIRP	
5.3.3.1 5.3.4		
3.3.4 5.3.4.1	ManagedEntity	
3.3.4.1 5.4		
5.4 5.4.1	Information relationship definitions	
5.4.1 5.4.1.1	relation-traceIRP-traceJob(M) Definition	
5.4.1.1 5.4.1.2		
5.4.1.2 5.4.2	relation-traceJob-managedEntity(M)	
5.4.2.1		
5.4.2.1 5.4.2.2		
5.4.2.2 5.4.3	relation-traceJob-traceRecord(M)	
5.4.3.1		
5.4.3.1 5.4.3.2		
5. 4 .5.2 5.5	Information attribute definitions	
5.5.1	Definition and legal values	
	-	
6 6 1	Interface Definition	
6.1 6.2	Class diagram representing interfaces	
6.2 6.3	Generic rules	
6.3.1	Operation activateTraceJob(M)	
6.3.1.1	* /	
6.3.1.1 6.3.1.2		
6.3.1.2		
6.3.1.4	1 1	

11.	(mornaerve). Change instory	
Anney A	(informative): Change history	3/
6.3.7.4	Constraint	33
6.3.7.3.2	To state	
6.3.7.3.1	From state	
6.3.7.3	Triggering event	
6.3.7.2	Input parameters	
6.3.7.1	Definition	
6.3.7	Notification notifyTraceSessionIdentities (CM)	
6.3.6.3.2	To state	
6.3.6.3.1	From state	
6.3.6.3	Triggering event	
6.3.6.2	Input parameters	
6.3.6.1	Definition	
6.3.6	$Notification \ \texttt{notifyTraceSessionLocalActivation} \ (M)$	
6.3.5.3.2	To state	
6.3.5.3.1	From state	
6.3.5.3	Triggering event	
6.3.5.2	Input parameters	
6.3.5.1	Definition	
6.3.5	Notification notifyTraceRecordingSessionFailure(0)	
6.3.4.3	Output parameters	
6.3.4.2	Input parameters	
6.3.4.1	Definition	
6.3.4	Operation listActivatedTraceJobs (M)	
6.3.3.7	Constraints	
6.3.3.6	Exceptions	
6.3.3.5	Post-condition	
6.3.3.4	Pre-condition	
6.3.3.3	Output parameters	
6.3.3.2	Input parameters	
6.3.3.1	Definition	
6.3.3	Operation listTraceJob (M)	
6.3.2.6	Exceptions	
6.3.2.4	Post-condition	
6.3.2.4	Pre-condition	
6.3.2.3	Output parameters	
6.3.2.2	Input parameters	
6.3.2.1	Definition	
6.3.2	Operation deactivateTraceJob (M)	
6.3.1.7	Constraints	
6.3.1.6	Exceptions	
6.3.1.5	Post-condition	
C 2 1 5	D	2.4

Foreword

This Technical Specification has been produced by the 3rd Generation Partnership Project (3GPP).

The contents of the present document are subject to continuing work within the TSG and may change following formal TSG approval. Should the TSG modify the contents of the present document, it will be re-released by the TSG with an identifying change of release date and an increase in version number as follows:

Version x.y.z

where:

- x the first digit:
 - 1 presented to TSG for information;
 - 2 presented to TSG for approval;
 - 3 or greater indicates TSG approved document under change control.
- y the second digit is incremented for all changes of substance, i.e. technical enhancements, corrections, updates, etc.
- z the third digit is incremented when editorial only changes have been incorporated in the document.

Introduction

The present document is part of a TS-family covering the 3rd Generation Partnership Project; Technical Specification Group Services and System Aspects; Telecommunication management; as identified below:

- 32.441 "Trace Management Integration Reference Point (IRP): Requirements".
- 32.442 "Trace Management Integration Reference Point (IRP): Information Service (IS)".
- 32.443 "Trace Management Integration Reference Point (IRP): Common Object Request Broker Architecture (CORBA) Solution Set (SS)".
- 32.445 "Trace Management Integration Reference Point (IRP): eXtensible Markup Language (XML) file format definition".

The present document is part of a TS-family which describes the information service necessary for the Telecommunication Management (TM) of 3G systems. The TM principles and TM architecture are specified in 3GPP TS 32.101 [1] and 3GPP TS 32.102 [2].

Trace provides very detailed information on call level for a specific subscriber or MS. This data is an additional information source to Performance Measurements and allows deeper investigations in problems solving or in case of optimization.

1 Scope

The present document describes the mechanism used for control and configuration of the Trace, Minimization of Drive Test (MDT) and Radio Link Failure (RLF) reporting functionality through Itf-N. This specification is applicable to UMTS networks and EPS networks. GSM Trace is outside of the scope of this specification.

The conditions for supporting Network Sharing are stated in 3GPP TS 32.441 [13].

2 References

The following documents contain provisions which, through reference in this text, constitute provisions of the present document.

- References are either specific (identified by date of publication, edition number, version number, etc.) or non-specific.
- For a specific reference, subsequent revisions do not apply.
- For a non-specific reference, the latest version applies. In the case of a reference to a 3GPP document (including a GSM document), a non-specific reference implicitly refers to the latest version of that document *in the same Release as the present document*.

[1]	3GPP TS 32.101: "Telecommunication management; Principles and high level requirements".
[2]	3GPP TS 32.102: "Telecommunication management; Architecture".
[3]	3GPP TS 32.150: "Telecommunication management; Integration Reference Point (IRP) Concept and definitions".
[4]	Void.
[5]	3GPP TS 32.622: "Telecommunication management; Configuration Management (CM); Generic network resources Integration Reference Point (IRP); Network Resource Model (NRM)".
[6]	3GPP TS 32.302: "Telecommunication management; Configuration Management (CM); Notification Integration Reference Point (IRP): Information Service (IS)".
[7]	3GPP TS 32.342: "Telecommunication management; File Transfer (FT) Integration Reference Point (IRP): Information Service (IS)".
[8]	3GPP TS 32.312: "Telecommunication management; Generic Integration Reference Point (IRP) management: Information Service (IS)".
[9]	3GPP TS 32.422: "Telecommunication management; Subscriber and equipment trace; Trace control and configuration management".
[10]	3GPP TS 32.602: "Telecommunication management; Configuration Management (CM); Basic CM Integration Reference Point (IRP): Information Service (IS)".
[11]	3GPP TS 25.331: "Radio Resource Control (RRC); Protocol specification"
[12]	3GPP TS 36.331: "Evolved Universal Terrestrial Radio Access (E-UTRA); Radio Resource Control (RRC); Protocol specification".
[13]	3GPP TS 32.441: "Trace Management Integration Reference Point (IRP): Requirements".
[14]	3GPP TS 36.300: "Evolved Universal Terrestrial Radio Access (E-UTRA) and Evolved Universal Terrestrial Radio Access Network (E-UTRAN); Overall description; Stage 2".

3 Definitions and abbreviations

3.1 Definitions

For the purposes of the present document, the terms and definitions given in 3GPP TS 32.101 [1], 3GPP TS 32.102 [2], 3GPP TS 32.150 [3] and the following apply:

IRPAgent: See 3GPP TS 32.102 [2].

IRPManager: See 3GPP TS 32.102 [2].MBSFN Area: See 3GPP TS 36.300 [14]

MBSFN Area Reserved Cell: See 3GPP TS 36.300 [14]

3.2 Abbreviations

For the purposes of the present document, the abbreviations given in 3GPP TS 32.101 [1], 3GPP TS 32.102 [2], 3GPP TS 32.150 [3] and the following apply:

IOC Information Object Class
IRP Integration Reference Point
IS Information Service

MBMS Multimedia Broadcast Multicast Services
MBSFN MBMS over a Single Frequency Network

MDT Minimization of Drive Tests
OMG Object Management Group

RCEF RRC Connection Establisment Failure

RLF Radio Link Failure

UML Unified Modelling Language (OMG)

4 System Overview

4.1 System context

The general definition of the System Context for the present IRP is found in 3GPP TS 32.150 [3] subclause 4.7.

In addition, the set of related IRP(s) relevant to the present IRP is shown in the two diagrams below.




Figure 4.1.1: System Context A




Figure 4.1.2: System Context B

4.2 Compliance rules

For general definitions of compliance rules related to qualifiers (Mandatory/Optional/Conditional) for *operations*, *notifications and parameters* (of operations and notifications) please refer to 3GPP TS 32.150 [3].

5 Information Object Classes

5.1 Imported information entities and local labels

Label reference	Local label
3GPP TS 32.622 [5], information object class, Top	Top
3GPP TS 32.622 [5], information object class, IRPAgent	IRPAgent
3GPP TS 32.622 [5], information object class, GenericIRP	GenericIRP
3GPP TS 32.302 [6], information object class, NotificationIRP	NotificationIRP
3GPP TS 32.342 [7], information object class, FileTransferIRP	FileTransferIRP
3GPP TS 32.602 [10], information object class, ManagedEntity	ManagedEntity

5.2 Class diagram

5.2.1 Attributes and relationships

This clause introduces the set of Information Object Classes (IOCs) that encapsulate information within the IRPAgent. The intent is to identify the information required for the TraceIRP implementation of its operations and notification emission. This clause provides the overview of all support object classes in UML. Subsequent clauses provide more detailed specification of various aspects of these support object classes.





Figure 5.2.1: Information Object Class (IOC) UML diagram

5.2.2 Inheritance






Figure 5.2.2: Information Object Class Inheritance UML Diagram

5.3 Information object class definitions

5.3.1 TraceJob

5.3.1.1 Definition

It represents a task that controls the Trace Sessions and collects the trace data (i.e. collects the TraceRecord of multiple ManagedEntity instances). The TraceReference is a unique ID, which identifies the Trace Session that has been created by the TraceJob and activated to one or multiple ManagedEntity instance(s).

It represents also the task that controls the UE based network performance measurements.

When a TraceJob is created the following attributes cannot be modified via the Itf-N:

- TraceReference
- ListOfInterfaces
- ListofNeTypes
- TraceDepth
- TraceTarget
- TriggeringEvent
- JobType
- areaScope
- ListOfMeasurements
- ReportingTrigger
- ReportInterval
- ReportAmount
- EventThreshold
- LoggingInterval
- LoggingDuration
- IPAddressOfTCE
- AnonymizationofMDTData
- MeasurementPeriodLTE
- MeasurementPeriodUMTS
- CollectionPeriodRrmUmts
- CollectionPeriodRrmLte
- PositioningMethod
- MeasurementQuantity
- PLMNTarget
- MBSFNAreaList

If for any reason the TraceIRP determines that a Trace Session has been activated in its ManagedEntity(ies) the TraceIRP shall emit the "noitfyTraceSessionLocalActivation" notification to the subscribed IRPManagers to inform the active Trace Sessions. The IRPManagers can decide whether they deactivate the Trace Session or keep the Trace Session active. (E.g. if the TraceReference is colliding with an existing TraceJob's TraceReference, the IRPManager may decide to immediately deactivate the Trace Session in that ManagedEntity.)

The TraceJob shall use its information to activate and configure Trace Session(s) in the requested ManagedEntity instance(s). When the TraceIRP determines that there are available TraceRecord files, it shall emit a notification to all subscribed IRPManagers informing the availability of the files. The method and the notification of the available files is described in the File Transfer IRP (3GPP TS 32.342 [7]).

If a TraceJob receives an indication from one of its ManagedEntity that starting a Trace Recording Session is failed for any reason, the "notifyTraceRecordingSessionFailure" notification may be emitted to inform all subscribed IRPManagers that there was a Trace Recording Session that was not started in the ManagedEntity.

5.3.1.2 Attributes

Attribute name	Support Qualifier
traceReference	M
listOfInterfaces	0
listOfNeTypes	CM
traceDepth	CM
traceTarget	M
triggeringEvent	CM
traceCollectionEntityAddress	M
jobType	M
listOfMeasurements	CM
reportingTrigger	CM
reportInterval	CM
reportAmount	CM
eventThreshold	CM
loggingInterval	CM
loggingDuration	CM
areaScope	CM
anonymizationOfMDTData	CM
measurementPeriodLTE	CM
measurementPeriodUMTS	CM
collectionPeriodRrmUmts	CM
collectionPeriodRrmLte	CM
positioningMethod	CM
measurementQuantity	CM
pLMNTarget	CM
mBSFNAreaList	CM

5.3.1.3 Attribute constraints

The listOfNeTypes attributes shall be present only for Signalling Based Activation.

The traceTarget shall be public ID in case of a Management Based Activation is done to an ScscfFunction. The TraceTarget shall be cell only in case of the UTRAN cell traffic trace function.

The TraceTarget shall be E-UtranCell only in case of E-UTRAN cell traffic trace function. The traceTarget shall be either IMSI or IMEI(SV) if the Trace Session is activated to any of the following ManagedEntity(ies):

- HssFunction
- MscServerFunction
- SgsnFunction
- GgsnFunction
- BmscFunction
- RncFunction
- MmeFunction

The traceTarget shall be IMSI if the Trace Session is activated to a ManagedEntity playing a role of ServinGWFunction.

In case of subscription based MDT, the traceTarget attribute shall be able to carry (IMSI or IMEI(SV)), the areaScope attribute shall be able to carry a list of (cell or EUtranCell or TA/LA/RA).

In case of area based Immediate MDT, the traceTarget attribute shall be null value, the areaScope attribute shall carry a list of (Utrancell or E-UtranCell).

In case of area based Logged MDT, the traceTarget attribute shall carry an eNodeBs or a RNC. The Logged MDT should be initiated on the specified eNodeB/RNC in TraceTarget. The areaScope attribute shall carry a list of (Utrancell or E-UtranCell or TA/LA/RA)..

In case of RLF reporting, or RCEF reporting, the traceTarget attribute shall be null value, the areaScope attribute shall carry one or list of eNBs.

- traceTarget: This attribute shall be present if Trace or MDT RLF or RCEF reporting is supported.
- areaScope: This attribute shall be present if MDT is supported.
- triggeringEvent: This attribute shall be present only if Trace is supported.
- listOfMeasurements: This attribute shall be present only if MDT is supported and the JobType attribute is set to ImmediateMDT.
- reportingTrigger: This attribute shall be present only if MDT is supported and the JobType attribute is set to ImmediateMDT and the ListOfMeasurements attribute is configured for M1 (for both UMTS and LTE) or M2 (only for UMTS).
- reportInterval: This attribute shall be present only if MDT is supported and the JobType attribute is set to ImmediateMDT and the ReportingTrigger is configured for PeriodicMeasurements
- reportAmount: This attribute shall be present only if MDT is supported and the JobType attribute is set to ImmediateMDT and the ReportingTrigger attribute is configured for PeriodicMeasurements.
- eventThreshold: This attribute shall be present only if MDT is supported and the JobType attribute is set to ImmediateMDT and the ReportTrigger attribute is configured for A2EventReporting in LTE or 1F/1IEventReporting in UMTS.
- loggingInterval: This attribute shall be present only if MDT is supported and the JobType attribute is set to LoggedMDT or Logged MBSFN MDT.
- loggingDuration: This attribute shall be present only if MDT is supported and the JobType attribute is set to LoggedMDT or Logged MBSFN MDT.
- anonymizationOfMDTData: This attribute shall be present only if MDT is supported and the mdtAreaScope attribute is present.
- measurementPeriodLTE: This attribute shall be present only if MDT is supported and the JobType attribute is set to Immediate MDT or combine Trace and Immediate MDT and the listOfMeasurements parameter for LTE has either M4 or M5 measurement set.
- measurementPeriodUMTS: This attribute shall be present only if MDT is supported and the JobType attribute is set to Immediate MDT or combine Trace and Immediate MDT and the listOfMeasurements parameter for UMTS has M6 or M7 measurements set.
- collectionPeriodRrmUmts: This attribute shall be present only if MDT is supported and the JobType attribute is set to Immediate MDT or combine Trace and Immediate MDT and the listOfMeasurements parameter has any of M3, M4, M5 measurement set in case of UMTS.
- collectionPeriodRrmLte: This attribute shall be present only if MDT is supported and the JobType attribute is set to Immediate MDT or combine Trace and Immediate MDT and the listOfMeasurements parameter has any of M2, M3 measurement set in case of LTE.
- positioningMethod: This attribute shall be present only if MDT is supported and the JobType attribute is set to Immediate MDT or combine Trace and Immediate MDT.
- measurementQuantity: This attribute shall be present only if MDT is supported and the JobType attribute is set to Immediate MDT or combined Trace and Immediate MDT and the reportingTrigger parameter is set to event 1F.

- pLMNTarget: This attribute shall be present for management based activation when several PLMNs are supported in the RAN.
- mbsfnarealist: This attribute shall be present only if Logged Mbsfn MDT is supported and the Jobtype attribute is set to Logged Mbsfn MDT. This is applicable only for eUTRAN.

5.3.2 TraceRecord

5.3.2.1 Definition

TraceRecord is the representation of the files containing the logged information from the Trace Recording Sessions.

5.3.2.2 Attributes

Attribute name	Visibility	Support Qualifier	Read Qualifier	Write Qualifier
fileName	+	M	M	-

5.3.3 TraceIRP

5.3.3.1 Definition

TraceIRPis the representation of the trace management capabilities specified by the present document. This IOC inherits from ManagedGenericIRP IOC specified in 3GPP TS 32.312 [8].

5.3.4 ManagedEntity

5.3.4.1 Definition

In case of Signalling Based Activation the ManagedEntity represents the role that can be played by an instance of one of the following IOCs:

- HssFunction
- MscServerFunction
- SgsnFunction
- MmeFunction

In case of Management Based Activation the ManagedEntity represents the role that can be played by an instance of the following IOCs:

- HssFunction
- MscServerFunction
- SgsnFunction
- GgsnFunction
- BmscFunction
- RncFunction
- CscfFunction
- MmeFunction
- ServingGWFunction

In case of Cell Traffic Trace the ManagedEntity represents the role that can be played by an instance of the following IOCs:

- UtranCell
- E-UtranCell

5.4 Information relationship definitions

5.4.1 relation-traceIRP-traceJob (M)

5.4.1.1 Definition

This represents the relationship between TraceIRP and the TraceJob.

5.4.1.2 Roles

Name	Definition
theTraceIRP	It represents the TraceIRP
theTraceJobList	It represents the TraceJobList

5.4.2 relation-traceJob-managedEntity (M)

5.4.2.1 Definition

This represents the relationship between TraceJob and the ManagedEntity.

5.4.2.2 Roles

Name	Definition		
theManagedEntity	The ManagedEntity, when playing this role, represents the actual network resource instanc		
	where a Trace Session is activated.		
theTraceJob	It represents the TraceJob		

5.4.3 relation-traceJob-traceRecord (M)

5.4.3.1 Definition

This represents the relationship between TraceJob and the TraceRecord.

5.4.3.2 Roles

Name	Definition
theTraceJob	It represents the TraceJob
theTraceRecord	It represnts the TraceRecord.

- 5.5 Information attribute definitions
- 5.5.1 Definition and legal values

Attribute Name	Definition	Legal Values
anonymizationOfMDTData	It specifies the level of anonymization for an area based MDT.	See 3GPP TS 32.422 [9]
areaScope	It specifies MDT area scope when activates an MDT job. For RLF and RCEF reporting it specifies the eNB or list of eNBs where the RLF or RCEF reports should be collected.	List of cells for area based Immediate MDT. Cell, TA, LA, RA are mutually exclusive. One or list of eNBs for RLF
collectionPeriodRrmLte	It specifies the collection period for collecting RRM configured measurement samples for M2, M3 in LTE. The attribute is applicable only for Immediate MDT. In case this attribute is not used, it carries a null semantic.	and RCEFreporting See 3GPP TS 32.422 [9]
collectionPeriodRrmUmts		See 3GPP TS 32.422 [9]
eventThreshold	It specifies the threshold which should trigger the reporting in case A2 event reporting in LTE or 1F/1I event in UMTS. The attribute is applicable only for Immediate MDT and when reportingTrigger is configured for A2 event in LTE or 1F event or 1I event in UMTS. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9] , 3GPP TS 25.331 [11] , 3GPP TS 36.331 [12]
jobType	It specifies the MDT mode and it specifies also whether the TraceJob represents only MDT, Logged MBSFN MDT, Trace or a combined Trace and MDT job. The attribute is applicable for Trace, MDT, RCEF and RLF reporting.	See 3GPP TS 32.422 [9]
listOfInterfaces	It specifies the interfaces that need to be traced in the given ManagedEntityFunction. The attribute is applicable only for Trace. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]
listOfMeasurements	It specifies the UE measurements that shall be collected in an Immediate MDT job. The attribute is applicable only for Immediate MDT. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]
listOfNETypes	It specifies in which type of ManagedFunction the trace should be activated. The attribute is applicable only for Trace with Signalling Based Trace activation. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]
loggingDuration	It specifies how long the MDT configuration is valid at the UE in case of Logged MDT. The attribute is applicable only for Logged MDT and Logged MBSFN MDT. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]
loggingInterval	It specifies the periodicty for Logged MDT. The attribute is applicable only for Logged MDT and Logged MBSFN MDT. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9], 3GPP TS 25.331 [11] , 3GPP TS 36.331 [12]
measurementPeriodLTE	It specifies the measurement period for the Data Volume and Scheduled IP throughput measurements for MDT taken by the eNB. The attribute is applicable only for Immediate MDT. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]

Attribute Name	Definition	Legal Values
measurementPeriodUMTS	It specifies the measurement period for the Data Volume and Throughput measurements for MDT taken by RNC. The attribute is applicable only for Immediate MDT. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]
measurementQuantity		See 3GPP TS 32.422 [9]
pLMNTarget		See 3GPP TS 32.422 [9]
positionigMethod	It specifies what positioning method should be used in the MDT job.	
reportAmount	It specifies the number of measurement reports that shall be taken for periodic reporting while the UE is in connected. The attribute is applicable only for Immediate MDT and when reportingTrigger is configured for periodical measurements. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]
reportInterval	It specifies the interval between the periodical measurements that shall be taken when the UE is in connected mode. The attribute is applicable only for Immediate MDT and when reportingTrigger is configured for periodical measurements. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]
reportingTrigger		See 3GPP TS 32.422 [9]
traceCollectionEntityAddress		See 3GPP TS 32.422 [9]
traceDepth		See 3GPP TS 32.422 [9]
traceReference		See 3GPP TS 32.422 [9]
traceTarget	It specifies the target object of the Trace and MDT. The attribute is applicable for both Trace and MDT. This attribute includes the ID type of the target and the ID value.	The ID type may be IMSI or IMEI or IMEISV or Public ID or Private ID or a Cell or an eNB or a RNC. The ID value can be a string. If the ID type is a Cell, the ID value can be identified by its DN id. IMSI, IMEI, IMEISV, Public ID, cell, eNB and RNC are mutually exclusive.
triggeringEvent	It specifies the triggering event parameter of the trace session. The attribute is applicable only for Trace. In case this attribute is not used, it carries a null semantic.	See 3GPP TS 32.422 [9]

Attribute Name	Definition	Legal Values
	The MBSFN Area consists of a MBSFN Area ID and Carrier Frequency (EARFCN). The target MBSFN area List can have up to 8 entries. This parameter is applicable only if the job type is Logged MBSFN MDT.	See 3GPP TS 32.422 [9]

6 Interface Definition

6.1 Class diagram representing interfaces




Figure 6.1: Class Diagram

6.2 Generic rules

- Rule 1: each operation with at least one input parameter supports a pre-condition valid_input_parameter which indicates that all input parameters shall be valid with regards to their information type. Additionally, each such operation supports an exception operation_failed_invalid_input_parameter which is raised when pre-condition valid_input_parameter is false. The exception has the same entry and exit state.
- **Rule 2:** each operation with at least one optional input parameter supports a set of pre-conditions supported_optional_input_parameter_xxx where "xxx" is the name of the optional input parameter and the pre-condition indicates that the operation supports the named optional input parameter. Additionally, each such operation supports an exception operation_failed_unsupported_optional_input_parameter_xxx which is raised when (a) the pre-condition supported_optional_input_parameter_xxx is false and (b) the named optional input parameter is carrying information. The exception has the same entry and exit state.
- **Rule 3:** each operation shall support a generic exception operation_failed_internal_problem which is raised when an internal problem occurs and that the operation cannot be completed. The exception has the same entry and exit state.

NOTE: These rules are mapped at the solution set level. Pre-conditions and exceptions, generated by these rules, need not appear explicitly in the present document.

6.3 TraceIRPManagement (M)

6.3.1 Operation activateTraceJob (M)

6.3.1.1 Definition

This operation support IRPManager's request to create a TraceJob through Itf-N.

Once the TraceJob has been created, the attributes of the TraceJob will not be modified during the lifetime of the TraceJob.

One TraceJob can manage Trace Sessions in one or more ManagedEntity.

6.3.1.2 Input parameters

Parameter Name	Qualifier	Information type	Comment
iOCInstance	М	ManagedEntity.objectInstance	It specifies the DN of
			ManagedEntity
			instance where Trace
			Session is to be
			activated.
listOfInterfaces	0	TraceJob.listOfInterfaces	1
listOfNeTypes	CM	TraceJob.listOfNeTypes	It specifies the type of
traceDepth	M	TraceJob.traceDepth	ManagedFunctions. It shows the
CraceDepth	IVI	raceoob.craceDepth	
			traceDepth set to the Trace Session.
traceReference	М	TraceJob.traceReference	It identifies the
crackererence	IVI	Traceous, cracencrerence	TraceSession.
traceTarget	М	TraceJob.traceTarget	IMSI or IMEI or
		_	IMEISV or Public ID
			or Private ID or a
			Cell(identified by its
			DN id) or an eNB or a
			RNC.
			IMSI, IMEI,
			IMEISV,Public ID, Cell, eNB and RNC
			are mutually
			exclusive.
triggeringEvent	СО	TraceJob.triggeringEvent	OXOIGOIVO.
traceCollectionEntityAddress		TraceJob.traceCollectionEntityAddress	It specifies the
		_	address to the Trace
			Collection Entity that
			is associated to the
			TraceJob. See
			3GPP TS 32.422 [9].
jobType	M	TraceJob.jobType	It specifies the type of the TraceJob
areaScope	CM	TraceJob.areaScope	It specifies MDT area
			(Cells/TA/RA/LA)
			where the Logged
			MDT measurements
			or Logged MBSFN
			MDT shall be
			collected. It specifies one or list
			of eNBs where the
			RLF or RCEF reports
			shall be collected.
			It specifies MDT area
			(list of cells) where
			the Immediate MDT
			measurements shall
7.1			be collected.
listOfMeasurements	CM	TraceJob.listOfMeasurements	It specifies the
			measurements to be collected from the UE
reportingTrigger	CM	TraceJob.reportingTrigger	It specifies the
1.0501.01113.11.133.01	CIVI	11466000.16401611131113461	reporting trigger
			(event based
			reporting or periodic
			reporting) in the UE.
reportInterval	CM	TraceJob.reportInterval	It specifies the
			interval between the
			periodical
			measurements to be
			taken by the UE.

Parameter Name	Qualifier	Information type	Comment
reportAmount	CM	TraceJob.reportAmount	It specifies the
			number of
			measurement reports
			to be taken in periodical reporting in
			the UE
eventThreshold	CM	TraceJob.eventThreshold	It specifies the
			threshold triggering
			the reporting in case
			of A2 event reporting
			in LTE or 1F/1I event reporting in UMTS.
loggingInterval	CM	TraceJob.loggingInterval	It specifies the
			periodicity of Logged
			MDT or Logged
			MBSFN MDT.
loggingDuration	CM	TraceJob.loggingDuration	It specifies the
			duration of the Logged MDT or
			Logged MBSFN MDT
			at the UE.
anonymizationOfMDTData	СМ	TraceJob.anonymizationOfMDTData	It specifies the
			anonymization level
			of an area based
	014		MDT.
measurementPeriodLTE	CM	TraceJob.measurementPeriodLTE	It specifies the
			measurement period for the Data Volume
			and Scheduled IP
			Throughput
			measurements in the
			eNB within an
measurementPeriodUMTS	СМ	TraceJob. measurementPeriodUMTS	Immediate MDT job. It specifies the
measurementperrodomis	Civi	illaceoob. measurementperrodomis	measurement period
			for the Data Volume
			and Throughput
			measurements in the
			RNC within an
collectionPeriodRrmUmts	CM	TraceJob.collectionPeriodRrmUmts	Immediate MDT job. It specifies the
correction erroant momes	Civi	Traces ob. correction crioant momes	collection period for
			M3, M4, M5 in UMTS
			within an Immediate
			MDT job.
collectionPeriodRrmLte	CM	TraceJob.collectionPeriodRrmLte	It specifies the
			collection period for M2, M3 in LTE within
			an Immediate MDT
			job.
positioningMethod	CO	TraceJob.positioningMethod	It specifies the
			positioning method to
			be used for the
measurementQuantity	СМ	TraceJob.measurementQuantity	Immediate MDT job. It specifies which
incapar cincility dailerty	CIVI	1140COOD. mcabatementQualitity	measurement should
			be collected in an
			event triggered
			measurement
			collection.
pLMNTarget	СМ	TraceJob.pLMNTarget	It specifies which PLMN that the
			subscriber of the
			session to be
			recorded uses as
			selected PLMN.
			

Parameter Name	Qualifier	Information type	Comment
mBSFNAreaList	СМ		It specifies MBSFN Area(s) for MBSFN MDT measurement logging.

6.3.1.3 Output parameters

Parameter Name	Qualifier	Matching Information	Comment
status	М	ENUM (Success, Failure, PartialSuccess)	
unsupportedList	М	List of <managedentity, td="" tracedepth,<=""><td>It specifies what attributes</td></managedentity,>	It specifies what attributes
		ListOfInterfaces, TraceTarget, areaScope,	are not supported when a
		listOfMeasurements,reportingTrigger,	Trace Session is activated.
		reportInterval,reportAmount,eventThreshold,	The list can contain one or
		loggingInterval, loggingDuration,	all of the elements and
		<pre>anonymizationOfMDTData, measurementPeriodLTE,</pre>	relevant only for error
		measurementPeriodUMTS, positioningMethod,	cases.
		measurementQuantity reason, pLMNTarget)	

6.3.1.4 Pre-condition

 $\verb|validTraceReference|| AND | \verb|validTraceDepth|| AND | \verb|validTraceTarget||$

Assertion Name	Definition
validTraceDepth	The traceDepth input parameter is valid.
	The traceReference given is not matching to any existing traceReference value in the activated TraceJobs.
validTraceTarget	The traceTarget input parameter is valid.

6.3.1.5 Post-condition

traceSessionActivated

Assertion Name	Definition	
traceSessionActivated	The Trace Session identified by the traceReference is activated in the given	
	ManagedEntity instances.	

6.3.1.6 Exceptions

Exception Name	Definition
invalidTraceDepth	Condition: (validTraceDepth) is false.
	Returned Information: output parameter status is set to "Failure".
	Exit state: Entry State.
invalidTraceTarget	Condition: (validTraceTarget) is false.
	Returned Information: output parameter status is set to "Failure".
	Exit state: Entry State.
notuniqueTraceReference	Condition: (validTraceReference) is false.
	Returned Information: output parameter status is set to "Failure".
	Exit state: Entry State.
pLMNTargetNotSupported	Condition: (validPLMNTarget) is false.
	Returned Information: output parameter status is set to "Failure".
	Exit state: Entry State.

6.3.1.7 Constraints

Name	Definition
listOfNeTypes	It is a Signalling Based Activated trace that is requested.
traceCollectionEntityAddress CM, CO qualifier	Mandatory when tracing in EPS is supported; Mandatory when MDT is supported; Optional when tracing in UMTS is supported.
areaScope	MDT is supported or RLF or RCEF reporting is supported
listOfMeasurements	MDT is supported
reportingTrigger	MDT is supported
reportInterval	MDT is supported
reportAmount	MDT is supported
eventThreshold	MDT is supported
loggingInterval	MDT is supported
loggingDuration	MDT is supported
listOfMeasurements	MDT is supported
traceDepth	Trace is supported
triggeringEvent	Trace is supported
anonymizationOfMDTData	MDT is supported
measurementPeriodLTE	MDT is supported
measurementPeriodUMTS	MDT is supported
collectionPeriodRrmUmts	MDT is supported
collectionPeriodRrmLte	MDT is supported
positioningMethod	MDT is supported

pLMNTarget	Several PLMNs are supported in the RAN and a Management Based Activation Trace Session is requested.
mBSFNAreaList	Logged MBSFN MDT is supported

6.3.2 Operation deactivateTraceJob (M)

6.3.2.1 Definition

This operation supports IPRManager's request to stop a TraceJob through Itf-N. When this operation is received in the TraceJob shall deactivate the requested Trace Session in the requested ManagedEntity instances.

6.3.2.2 Input parameters

Parameter Name	Qualifier	Information type	Comment
traceReference	M	TraceJob.traceReference	This is a unique ID of the TraceJob
traceTarget	М	_	(IMSI or IMEI or IMEISV or Public ID or Private ID or a Cell(identified by its DN id) or an eNB or a RNC. IMSI, IMEI, IMEISV,Public ID, Cell, eNB and RNC are mutually exclusive.

6.3.2.3 Output parameters

Parameter Name	Qualifier	Matching	Comment
		Information	
status	M	ENUM (Success,	The operation may fail because of a specified
		Failure)	or an unspecified reason.
traceRecordingSessionReference	CM		This would indicate if a Trace Recording
			Session is ongoing when the deactivation
			command has been given.

6.3.2.4 Pre-condition

validTraceReference

Assertion Name	Definition
	The TraceReference input parameter is valid, which means that the TraceIRP is aware of such TraceJob, which has this traceReference value and is aware of the ManagedEntity holding such Trace Session.

6.3.2.4 Post-condition

TraceSessionisdeactivated

Assertion Name	Definition
	The Trace Session identified by the traceReference is deactivated in the
	requested ManagedEntity instance and the TraceJob is stopped.

6.3.2.6 Exceptions

Exception Name	Definition
notuniqueTraceReference	Condition: (validTraceReference) is false.
	Returned Information: output parameter status is set to "Failure".
	Exit state: Entry State.

6.3.3 Operation listTraceJob (M)

6.3.3.1 Definition

This operation support IPRManager's request to list the parameters of a specific TraceJob through Itf-N.

6.3.3.2 Input parameters

Parameter Name	Qualifier	Information type	Comment
traceReference	М	TraceJob.traceReference	It specifies the Trace Session that is requested for
			interrogation.

6.3.3.3 Output parameters

tInstance I fraces of traceJob.listofInter faces I fraces of traceJob.listofInter faces I fraces of the process	Parameter Name	Qualifier	Matching Information	Comment
IstofInterface Status	i0CInstance	M	ManagedElement.objec	It specifies the DN of ManagedElement instance where
faces faces configuration parameter that is associated with the TraceJob. See 3GPP TS 32 422 [9] Status M ENUM (Success, Failure) traceDepth M TraceJob. traceDepth braceRecordings CM Espointerference traceRecordings CM TraceJob. traceTarget M TraceJob. traceTarget CM TraceJob. traceTarget CM TraceJob. traceCollection traceCollection CM, CO TraceJob. traceCollection traceToptings mutually exclusive. CM TraceJob. traceCollection traceToptings maceScope CM TraceJob. areaScope CM TraceJob. braceCollection traceToptingsTrigge TraceJob. areaScope CM TraceJob. braceCollection TraceJob. areaScope CM TraceJob. areaScope CM TraceJob. areaScope CM TraceJob. areaScope CM TraceJob. areaScope TraceJob. areaScope CM TraceJob. areaScope CM TraceJob. areaScope CM TraceJob. areaScope TraceJob. areaScope CM TraceJob. areaScope TraceJob. areaScope CM TraceJob. areaScope TraceJob. areaScope TraceJob. areaScope CM TraceJob. areaScope Trace				
Status		0		
TracePoth	S		faces	
traceDepth M TraceJob.traceDepth It shows the traceDepth trace control and configuration parameter that is associated to the TraceJob is parameter that is associated to the TraceJob. TraceJob is parameter that is associated to the TraceJob is parameter that is parameter that is associated to the TraceJob is parameter that is parameter that is associated to the TraceJob is parameter that is parameter that is associated to the TraceJob is parameter that is parameter that is associated to the TraceJob is par		<u> </u>		
traceRecording essionReference traceTarget M TraceJob.traceTarget M TraceJob.traceTarget M TraceJob.traceTarget M TraceJob.traceTarget M TraceJob.traceTarget CO TraceJob.traceTarget CO TraceJob.traceTarget TraceJob.traceTarget CM TraceJob.traceTarget CM TraceJob.traceTarget M TraceJob.traceTarget CM TraceJob.traceTarget CM TraceJob.traceTarget CM TraceJob.traceTarget M TraceJob.traceTarget CM TraceJob.traceCollection RhityAddress JobType M TraceJob.traceCollection RhityAddress M TraceJob.traceCollection RhityAddress M TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.traceCollection Areascope CM TraceJob.traceCollection Areascope Areascope CM TraceJob.traceCollection Areascope Areascope CM TraceJob.traceCollection Areascope Area	Status	M	ENUM (Success, Failure)	
parameter that is associated to the TraceJob. This would indicate if a Trace Recording Session is ongoing when the deactivation command has been giver in the control of th	tragoDonth	NA	Trace Tob traceDonth	
traceRecordings easi onReference traceTarget M TraceJob.traceTarget M TraceJob.traceTarget M TraceJob.traceTarget M TraceJob.traceTarget M TraceJob.traceTarget CO TraceJob.traceTarget CO TraceJob.traceTarget CO TraceJob.traceCarget TraceJob.traceCarget CO TraceJob.traceCarget CM, CO TraceJob.traceCarget TraceJob.traceCollection EntityAddress jobType M TraceJob.jobType M TraceJob.jobType TraceJob.traceCollection Areason TraceJob.traceCollection Areason Areason CM TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.areaScope TraceJob.traceCollection TraceJob.traceCollection TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.areaScope TraceJob.traceCollection TraceJob.traceCollection	craceDepth	IVI	liaceJob.traceDepth	
easionReference traceTarget M TraceJob.traceTarget M	tragoPogordingC	CM		,·
traceTarget M TraceJob.traceTarget CO TraceJob.traceTarget CO TraceJob.traceTarget TraceJob.traceTarget CO TraceJob.traceTarget CO TraceJob.traceCollection CM,CO TraceJob.traceCollection CM,CO TraceJob.traceCollection TraceJob.see GSPP TS 32.422 [9] TraceJob.get TraceJob.get TraceJob.traceCollection TraceJob.traceCollection TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.traceCollection TraceJob.traceCollection TraceJob.traceCollection TraceJob.traceCollection TraceJob.areaScope CM TraceJob.areaScope CM TraceJob.areaScope TraceJob.traceCollection TraceJob.trac		CIVI		
Cell (identified by its DN id) or an eNB or a RNC. MSI, IMEI, MEISV, Public ID, Cell, eNB and RNC are mutually exclusive. It is pecifies the triggering event trace control and configuration parameter that is associated to the TraceJob. braceCollect it inshrityAddress jobType M TraceJob. jobType TraceJob. jobType TraceJob. areaScope CM TraceJob. areaScope CM TraceJob. areaScope TraceJob. areaScope CM TraceJob. areaScope TraceJob. areaScope CM TraceJob. is typecifies the properting. RCEF reporting. It specifies MDT area (Isl of Cells) where the RLF reports, or RCEF reports shall be collected. It specifies MDT area (Isl of Cells) where the RLF reports, or RCEF reportingTrigge TraceJob. reportInter inger TraceJob. reportInter inger TraceJob. reportAmount CM TraceJob. reportAmount CM TraceJob. reportAmount CM TraceJob. loggingInter to the reporting in the UE. TraceJob. loggingInterval loggingInterval CM TraceJob. loggingInter CM TraceJob. anonymizati onOfMDTData measurementPeri odLTE CM TraceJob. anonymizati indUMTS CollectionPerio CM TraceJob. collectionPerio dArmalums CM TraceJob. collectionPerio dArmalums CM TraceJob. positioning METHORITAGE CM TraceJob. positioning Method CM TraceJob. positioning Method CM TraceJob. plaNtyTarget CM TraceJob. plantyTarg		M	TraceJob.traceTarget	
triggeringEvent CO TraceJob.triggeringE vent configuration parameter that is associated to the TraceSob. See 3GPP TS 32.422 [9]. traceCollection CM,CO TraceJob.traceCollect is the specifies the triggering event trace control and configuration parameter that is associated to the TraceJob. See 3GPP TS 32.422 [9]. traceCollection CM,CO TraceJob.jobType	01400141900	'''		
triggeringEvent CO TraceJob.triggeringEvent vent CM,CO TraceJob.triggeringEvent vent TraceJob.se 3GPP TS 32.422 [8] It specifies the address to the Trace Collection Entity that is associated to the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies the type of the TraceJob. See 3GPP TS 32.422 [8] It specifies MD Trace It is following: Trace Vent TraceJob. It also collected. It specifies MDT arace It is oblication with See It is specifies MDT arace It is oblication with See It is specifies the measurement periodical measurements to be taken by the UE. It specifies the threshold triggering the reporting in Case of A2 event reporting in LTE or 1F/11				
traceCollection EntityAddress piobType M TraceJob.traceCollect EntityAddress piobType M TraceJob.jobType M TraceJob.areaScope CM Trac				
traceCollection CM,CO TraceJob.traceCollection EntityAddress icionEntityAddress is associated to the TraceCollection Entity that EntityAddress is associated to the TraceCollection Entity that EntityAddress is associated to the TraceCollection Entity that EntityAddress is associated to the TraceCollection Entity that is provided to the TraceCollection Entity that EntityAddress is associated to the TraceCollection Entity that EntityAddress is associated to the TraceCollection Entity that Entity Entit	twiggowingErront	CO	TraceJob.triggeringE	It specifies the triggering event trace control and
traceCollection CM,CO TraceJob.traceCollect tionEntityAddress jobType M TraceJob.jobType M TraceJob.jobType M TraceJob.jobType It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the type of the TraceJob. Sea 32.422 [9] It specifies the TraceJob. TraceJob MDT measurements shall be collected. It specifies MDT area (Cells) Awhere the Logge MDT measurements shall be collected. It specifies MDT area (Ist of cells) where the Immediate MDT measurements shall be collected. It specifies the reportable to expect the specifies the reporting trigger (event based reporting or periodic reporting) in the UE. It specifies the reporting trigger (event based reporting or periodic reporting) in the UE. TraceJob.reportInter it specifies the interval between the periodical measurements to be taken by the UE. TraceJob.pologgingInterval CM TraceJob.loggingInterval CM TraceJob.measurement TraceJob.measurement TraceJob.measurement TraceJob.measurement TraceJob.measurement TraceJob.measurement TraceJob.measurement TraceJob.measurement TraceJob.positioning measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. TraceJob.positioning eriod measurement should be used for the Immediate MDT job. TraceJob.positioning and It specifies which measurements in the OBA Immediate MDT job. TraceJob.positioning and Immediate MDT job. TraceJob.positioning and Immediate MDT job. TraceJob.positioning and Immediate M	triggering Event		vent	
EntityAddress tionEntityAddress is associated to the TraceJob. See 3GPP TS 32.422 [9] jobType M TraceJob.jobType It specifies the type of the TraceJob. It can be one of the following: Trace, MDT data collection, Trace and MDT data collection, RLF reporting, RCEF reporting. areaScope CM TraceJob.areaScope It specifies MDT area (Cells/TA/A/A) where the Logge MDT measurements shall be collected. It specifies one or list of eNBs where the RLF reports, or RCEF reports shall be collected. It specifies one or list of cells) where the lumediate MDT measurements shall be collected. It specifies one or list of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies the reporting in the UE that shall be collected with the specifies were a first of cells where the RLF reports, or RCEF reports shall be collected. It specifies the reporting in the UE that shall be collected with the State of the RCEF reports where the RLF reports were the specifies were the RLF reporting o				
It specifies the type of the TraceJob. It can be one of the following: Trace, MDT data collection, Trace and MDT data collection, Trace and MDT data collection, RLF reporting, RCEF reporting. RCEF reporting to the LCgels. RCEF reportis in the RCE reports. RCEF reports and It specifies the reporting ties the RCEF reports. It specifies the reporting to event the UE event Thresh to plant the UE. TraceJob. loggingInter to Lake in preiodical reporting in the UE. TraceJob. loggingInter to Lake in preiodical reporting in the UE. TraceJob. loggingInter to Logged MIDTs. It specifies the duration of the Logged MIDTs. It specifies the duration of the Logged MIDTs. It specifies the duration of the Logged MIDT at the UE. TraceJob. anonymizati it specifies the measurement period for the Data Volume and Throughput m		CM,CO		
areaScope CM TraceJob.areaScope				
data collection, RLF reporting, RCEF reporting, areaScope CM TraceJob.areaScope Trac	jobType	M	TraceJob.jobType	
areaScope CM TraceJob.areaScope It specifies MDT area (Cells/TA/RA/LA) where the Logge MDT measurements shall be collected. It specifies one or list of eNBs where the RLF reports, or RCEF reports shall be collected. It specifies to really where the Interval provided in the Collected of the Collection of				
MDT measurements shall be collected. It specifies one or list of eNBs where the RLF reports, or RCEF reports shall be collected. It specifies one or list of eNBs where the RLF reports, or RCEF reports shall be collected. It specifies MDT area (list of cells) where the Immediate MDT measurements and list of cells) where the Immediate MDT measurements of the collected. It specifies the measurements to be collected from the U rements CM TraceJob.reportIngTr it specifies the reporting trigger (event based reporting of periodic reporting) in the UE. TraceJob.reportIner it specifies the interval between the periodical measurements to be taken by the UE. TraceJob.reportAmount it specifies the number of measurement reports to be taken in periodical reporting in the UE. TraceJob.eventThresh old UMTS in LTE or 1F/11 event reporting in case of A2 event reporting in LTE or 1F/11 event reporting in UMTS. LoggingInterval CM TraceJob.loggingInter in the Specifies the periodicity of the logging for dowlink pilot strength measurement in Logged MDT at the UE. TraceJob.measurement in Logged MDT at the UE. TraceJob.measurement in Logged MDT at the UE. TraceJob.measurement in the specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. TraceJob.collectionPerio CM TraceJob.collection in the measurement period for M3, M4, M5 in UMTS collectionPerio CM TraceJob.collection in the prositioning Method Metho	awaa Caana	CM	Two go Tob owoo Cgopo	
It specifies one or list of eNBs where the RLF reports, or RCEF reports shall be collected. It specifies MDT area (list of cells) where the Immediate MDT measurements shall be collected. It specifies the measurements to be collected from the Unit proper trace of the periodic reporting trigger (event based reporting or periodic reporting) in the UE. TraceJob.reportInter It specifies the reporting trigger (event based reporting or periodic reporting) in the UE. TraceJob.reportInter It specifies the interval between the periodical measurements to be taken by the UE. TraceJob.reportAmount It specifies the interval between the periodical measurement reports to be taken in periodical reporting in the UE. TraceJob.reportAmount It specifies the interval between the periodical measurement reports to be taken in periodical reporting in the UE. TraceJob.eventThresh It specifies the interval between the periodical measurement reports to be taken in periodical reporting in the UE. TraceJob.loggingInter It specifies the interval between the periodical measurement reports to be taken in periodical reporting in the UE. TraceJob.loggingInter It specifies the interval between the periodical measurement reports to be taken in periodical reporting in the UE. TraceJob.loggingInter It specifies the interval between the periodical reporting in case of A2 event reporting in LTE or 1F/11 event reporting in CAB event reporting in LTE or 1F/11 event reporting in UMTS in LTE or 1F/11 eve	areascope	CIVI	liaceJob.areascope	
RCEF reports shall be collected. It specifies MDT area (list of cells) where the Immediate MDT measurements shall be collected. It specifies the measurements to be collected from the Units rements reportingTrigge CM TraceJob.reportingTr it specifies the reporting trigger (event based reporting or periodic reporting) in the UE. reportInterval CM TraceJob.reportInter val val reportAmount to the telephone val reportInters be taken in periodical reporting in the UE. reportAmount CM TraceJob.reportAmoun to the telephone val reporting in the UE. reportAmount CM TraceJob.eventThresh old CM TraceJob.eventThresh old CM TraceJob.eventThresh old UMTS in LTE or 1f/1event reporting in case of A2 event reporting in LTE or 1f/1event reporting in UMTS. loggingInterval CM TraceJob.loggingInte reval tion loggingDuration CM TraceJob.loggingDura tion CM TraceJob.anonymizati onofMDTData onofMDTData measurementPeri odUTE CM TraceJob.measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob.collectionPeriodMTMs ceriodRrmUths collectionPeriod RrmUths collectionPerio CM TraceJob.collectionPeriodRrmUths collectionPerio CM TraceJob.positioning it specifies the collection period for M2, M3 in LTE within an Immediate MDT job. CM TraceJob.positioning it specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. CM TraceJob.positioning it specifies the collection period for M2, M3 in LTE within an Immediate MDT job. CM TraceJob.positioning it specifies the positioning method to be used for the Immediate MDT job. CM TraceJob.positioning it specifies which measurement should be collected in an event triggered measurement collection. Expecifies MBSFN Area(s) for MBSFN MDT It specifies SMiSFN Area(s) for MBSFN MDT				
It specifies MDT area (list of cells) where the Immediate MDT measurements shall be collected. It specifies the measurements to be collected from the U rements or igger periodic reporting trigger (event based reporting or periodic reporting) in the UE. TraceJob.reportInter val collection periodic reporting to periodic reporting in the UE. TraceJob.reportInter val collection periodic reporting in the UE. It specifies the interval between the periodical measurements to be taken by the UE. TraceJob.reportAmount to the text of the text of the collection periodic reporting in the UE. TraceJob.reportAmount to the text of the collection periodical reporting in the UE. TraceJob.eventThreshold to the UE to taken in periodical reporting in UMTS in LTE or 1F/1l event reporting in Case of A2 event reporting in UMTS. It specifies the periodicity of the logging for dowlink pilot strength measurement in Logged MDT. It specifies the duration of the Logged MDT at the UE.				
MDT measurements shall be collected.				
rements reportingTrigge				
reportingTrigge reportInterval CM TraceJob.reportInterval tspecifies the reporting trigger (event based reporting or periodic reporting) in the UE. reportAmount CM TraceJob.reportAmount tspecifies the interval between the periodical measurements to be taken by the UE. reportAmount CM TraceJob.reportAmount tspecifies the interval between the periodical measurements to be taken by the UE. reportAmount CM TraceJob.reportAmount tspecifies the interval between the periodical measurement reports to be taken in periodical reporting in the UE. reportAmount CM TraceJob.eventThresh old characteristics and the periodical reporting in the UE. reportAmount CM TraceJob.eventThresh old characteristics and the periodical reporting in the UE. reportAmount tspecifies the unmber of measurement reports to be taken by the UE. It specifies the threshold triggering the reporting in case of A2 event reporting in LTE or 1F/1I even	listOfMeasureme	CM	TraceJob.listofMeasu	It specifies the measurements to be collected from the UE
reportInterval CM TraceJob.reportInter lt specifies the interval between the periodical measurements to be taken by the UE. reportAmount CM TraceJob.reportAmoun lt specifies the number of measurement reports to be taken in periodical reporting in the UE lt specifies the number of measurement reports to be taken in periodical reporting in the UE lt specifies the threshold triggering the reporting in case of A2 event reporting in LTE or 1F/11 event reporting in UMTS in LTE or 1F/11 event reporting in UMTS. loggingInterval CM TraceJob.loggingIntel tryal lt specifies the periodicity of the logging for dowlink pilot strength measurement in Logged MDT. loggingDuration CM TraceJob.loggingDura lt specifies the duration of the Logged MDT at the UE. anonymizationOf CM TraceJob.anonymizati onOfMDTData measurementPeri odLTE lt specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob.collectionPeriodRrmUmts collectionPeriodRrmUmts eriodRrmUmts within an Immediate MDT job. CM TraceJob.collectionPeriodRrmUmts collectionPeriodRrmUmts eriodRrmUmts eriodRrmUmte and Immediate MDT job. CM TraceJob.positioning Method lt specifies the positioning method to be used for the measurement should be collected in an event triggered measurement collection. It specifies the collection period for M2, M3 in LTE within an Immediate MDT job. It specifies the positioning method to be used for the lmmediate MDT job. CM TraceJob.positioning lt specifies the positioning method to be used for the lmmediate MDT job. CM TraceJob.measurement lt specifies which measurement should be collected in an event triggered measurement collection. It specifies MBSFN Area(s) for MBSFN MDT	nts			
reportInterval CM TraceJob.reportInter val measurements to be taken by the UE. reportAmount CM TraceJob.reportAmount t specifies the number of measurement reports to be taken in periodical reporting in the UE. reventThreshold CM TraceJob.eventThresh old TraceJob.loggingInterval comparison of A2 event reporting in LTE or 1F/1I event reporting in UMTS in LTE or 1F/1I event reporting in UMTS in LTE or 1F/1I event reporting in UMTS. loggingInterval CM TraceJob.loggingInterval tion anonymization CM TraceJob.loggingDural tion TraceJob.loggingDuration CM TraceJob.anonymizati confMDTData confMDTData measurementPeri odLTE CM TraceJob.measurement PeriodUTE collectionPeriodUMTS measurementPeri odUMTS CM TraceJob.collectionPeriod CM TraceJob.collectionPeriod CM TraceJob.positioning od measurement Quantity TraceJob.planNTarget CM TraceJob.planNTarget It specifies which measurement should be collected in an event triggered measurement collection. It specifies which PLMN that the subscriber of the sessic to be taken by the UE. It specifies the number of measurement periods to teperiodical reporting in the UE It specifies the threshold triggering the reporting in case of A2 event reporting in the UE It specifies the periodicity of the logging for dowlink pilot strength measurement in Logged MDT. It specifies the duration of the Logged MDT at the UE. It specifies the anonymization level of an area based MDT. It specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. It specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. It specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. It specifies the positioning method to be used for the measurement Quantity event triggered measurement should be collected in an event triggered measurement collection. It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN.	reportingTrigge	СМ		
reportAmount CM TraceJob.reportAmount lt specifies the number of measurement reports to be taken by the UE. reportAmount CM TraceJob.eventThresh lt specifies the number of measurement reports to be taken in periodical reporting in the UE eventThreshold CM TraceJob.eventThresh lt specifies the threshold triggering the reporting in case of A2 event reporting in LTE or 1F/1I event reporting in UMTS. loggingInterval CM TraceJob.loggingIntel ts specifies the periodicity of the logging for dowlink pilot strength measurement in Logged MDT. loggingDuration CM TraceJob.loggingDura lt specifies the periodicity of the logging for dowlink pilot strength measurement in Logged MDT. It specifies the duration of the Logged MDT at the UE. It specifies the anonymization level of an area based MDT. It specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob. collectionPriodUMTS CollectionPeriod CM TraceJob.collectionP eriodRrmUmts collectionPeriod CM TraceJob.collectionP eriodRrmLte positioningMeth collectionPeriod CM TraceJob.positioning od Method measurementQuan tity pLMNSTarget CM TraceJob. pLMNTarget It specifies the collection period for M2, M3 in LTE within an Immediate MDT job. It specifies the positioning method to be used for the measurement collection. It specifies which PLMN that the subscriber of the sessic to be recorded uses as selected PLMN. It specifies MBSFN Area(s) for MBSFN MDT	r	014		
reportAmount CM	reportInterval	СМ		
eventThreshold CM TraceJob.eventThresh old CM TraceJob.eventThresh old CM TraceJob.eventThresh old CM TraceJob.eventThresh old CA event reporting in LTE or 1F/1I event reporting in UMTS. loggingInterval CM TraceJob.loggingIntel rval Strength measurement in Logged MDT. loggingDuration CM TraceJob.loggingDura It specifies the periodicity of the logging for dowlink pilot strength measurement in Logged MDT. loggingDuration CM TraceJob.loggingDura It specifies the duration of the Logged MDT at the UE. tion It specifies the anonymization level of an area based MDT. measurementPeri odLTE Strength measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob. measurementPeriodUMTS Strength measurement period for the Data Volume and Throughput measurements in the RNC within an Immediate MDT job. collectionPerio CM TraceJob.collectionPeriodRrmLte eriodRrmLte within an Immediate MDT job. CM TraceJob.positioning It specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. TraceJob.positioning It specifies the periodicity of the logging for dowlink pilot strength measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. TraceJob.collectionPerio CM TraceJob.collection period for M3, M4, M5 in UMTS within an Immediate MDT job. TraceJob.positioning It specifies the collection period for M2, M3 in LTE within an Immediate MDT job. TraceJob.positioning It specifies which measurement should be collected in an immediate MDT job. TraceJob.positioning It specifies which measurement should be collected in an event triggered measurement collection. TraceJob.plMNTarget It specifies which PLMN that the subscriber of the sessic to be recorded uses as selected PLMN. It specifies MBSFN Area(s) for MBSFN MDT	report Amount	CM	1 11	
TraceJob. eventThresh old Septimental old Septiment Sept	Tepor camount	Civi		
old of A2 event reporting in LTE or 1F/1I event reporting in UMTS CM TraceJob.loggingInterval traceJob.loggingInterval traceJob.loggingInterval traceJob.loggingInterval traceJob.loggingDuration CM TraceJob.loggingDura traceJob.loggingDura traceJob.anonymizationOf MDTData traceJob.measurement DeriodLTE TraceJob.measurement DeriodLTE TraceJob.measurement DeriodLTE CM TraceJob.measurement DeriodLTE TraceJob.measurement DeriodLTE TraceJob.measurement DeriodLTE TraceJob.measurementPeriodUMT So DeriodCollectionPeriodLTE SollectionPeriodLTE TraceJob.collectionPeriodCollectionPeriodLTE DeriodLTE DeriodLTE SollectionPeriodLTE DeriodLTE DeriodLTE SollectionPeriodLTE DeriodLTE SollectionPeriodLTE SollectionPeriodLTE DeriodLTE DeriodLTE SollectionPeriodLTE DeriodLTE DeriodLTE DeriodLTE DeriodLTE DeriodLTE DeriodLTE DeriodLTE SollectionPeriodLTE DeriodLTE DeriodL	eventThreshold	CM	TraceJob.eventThresh	
UMTS in LTE or 1F/II event reporting in UMTS. CM TraceJob.loggingInter tyal strength measurement in Logged MDT. CM TraceJob.loggingDuration CM TraceJob.anonymizati onOfMDTData in Expecifies the duration of the Logged MDT at the UE. TraceJob.anonymization lts specifies the anonymization level of an area based MDT. TraceJob.measurement beriod of the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob.anonymization lts specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob.collectionPeriodal Its specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. CM TraceJob.positioning lts specifies the collection period for M2, M3 in LTE within an Immediate MDT job. TraceJob.positioning lts specifies the positioning method to be used for the Immediate MDT job. TraceJob.measurement lts pecifies which measurement should be collected in an Immediate MDT job. TraceJob.measurement lts pecifies which measurement should be collected in an Immediate MDT job. TraceJob.plantarget lts specifies which measurement collection. TraceJob.plantarget lts specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. Its specifies MBSFN Area(s) for MBSFN MDT				
traceJob.loggingDuration CM TraceJob.loggingDura It specifies the duration of the Logged MDT at the UE. TraceJob.anonymizati onOfMDTData measurementPeri odLTE measurementPeri odUMTS collectionPerio dRrmUmts collectionPerio dRrmLte positioningMeth od measurementQuan tity pLMNTarget CM TraceJob. measurement priod for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. It specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. It specifies the measurement period for the Data Volume and Throughput measurements in the RNC within an Immediate MDT job. CM TraceJob.collectionP It specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. CM TraceJob.positioning of the positioning method to be used for the Immediate MDT job. CM TraceJob.measurement traceJob.measurement traceJob.positioning of the Immediate MDT job. CM TraceJob.measurement traceJob.measurement traceJob.positioning of the Immediate MDT job. CM TraceJob.measurement traceJob.measurement traceJob.positioning of the Session to be recorded uses as selected PLMN. TraceJob. MBSFNArea(s) for MBSFN MDT				UMTS in LTE or 1F/1I event reporting in UMTS
trval strength measurement in Logged MDT. TraceJob.loggingDura it specifies the duration of the Logged MDT at the UE. TraceJob.anonymizati onof MDTData MDT. TraceJob.measurement beriodLTE Measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. TraceJob. ollectionPeriodLTE Schemensurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. TraceJob. ollectionPeriodLTE Schemensurement period for the Data Volume and Throughput measurements in the eNE within an Immediate MDT job. TraceJob.collectionPeriodLTE Schemensurement period for M3, M4, M5 in UMTS within an Immediate MDT job. TraceJob.collectionPeriodLTE Schemensurement period for M3, M4, M5 in UMTS within an Immediate MDT job. TraceJob.collectionPeriodLTE Schemensurement period for M2, M3 in LTE within an Immediate MDT job. TraceJob.measurement periodLTE Schemensurement period for M2, M3 in LTE within an Immediate MDT job. TraceJob.measurement periodLTE Schemensurement period for M2, M3 in LTE within an Immediate MDT job. TraceJob.measurement periodLTE Schemensurement period for M2, M3 in LTE within an Immediate MDT job. TraceJob.measurement periodLTE Schemensurement period for M2, M3 in LTE within an Immediate MDT job. TraceJob.measurement periodLTE specifies the positioning method to be used for the Immediate MDT job. TraceJob.measurement periodLTE specifies which measurement period for M2 periodLTE specifies which measurement period for M3 periodLTE specifies which measurement periodLTE specifies which PLMN that the subscriber of the session to be recorded uses as se	loggingInterval	CM	TraceJob.loggingInte	It specifies the periodicity of the logging for dowlink pilot
anonymizationOf MDTData			rval	strength measurement in Logged MDT.
anonymizationOf MDTData onOfMDTData (MDT.) measurementPeri odLTE	loggingDuration	СМ		It specifies the duration of the Logged MDT at the UE.
measurementPeri odLTE CM TraceJob.measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob.		CM		
TraceJob.measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob. measurementPeriodUMT S It specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. It specifies the measurement period for the Data Volume and Throughput measurements in the RNC within an Immediate MDT job. CollectionPerio dRrmUmts within an Immediate MDT job. CollectionPerio dRrmLte eriodRrmLte eriodRrmLte an Immediate MDT job. TraceJob.collectionPerio draceJob.positioning Method It specifies the collection period for M2, M3 in LTE within an Immediate MDT job. It specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. It specifies the measurement period for the Data Volume and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. It specifies the measurement period for the Data Volume and Throughput measurements in the eNE within an Immediate MDT job. It specifies the measurement period for the Data Volume and Throughput measurements in the eNE within an Immediate MDT job. It specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. It specifies the positioning method to be used for the Immediate MDT job. It specifies which measurement collection. It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. It specifies MBSFN Area(s) for MBSFN MDT		CIVI		
periodLTE PeriodLTE and Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. CM TraceJob. measurementPeriodUMTS collectionPerio dRrmUmts collectionPerio dRrmLte positioningMeth od measurementQuan tity pLMNTarget CM TraceJob. periodLTE And Scheduled IP Throughput measurements in the eNE within an Immediate MDT job. It specifies the measurements in the RNC within an Immediate MDT job. It specifies the collection period for M3, M4, M5 in UMTS within an Immediate MDT job. It specifies the collection period for M2, M3 in LTE within an Immediate MDT job. It specifies the positioning method to be used for the Immediate MDT job. It specifies which measurement should be collected in an event triggered measurement collection. It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. It specifies MBSFN Area(s) for MBSFN MDT		CM		
within an Immediate MDT job. CM TraceJob. measurementPeriodUMT S Immediate MDT job. COM TraceJob.collectionP dRrmUmts CollectionPerio dRrmLte positioningMeth od measurementQuan tity pLMNTarget CM TraceJob. measurement CM TraceJob. measurement CM TraceJob. collectionP draceJob. collectionP deriodRrmLte TraceJob. pLMNTarget CM TraceJob. measurement CM TraceJob. pLMNTarget CM TraceJob. pLMNTarget CM TraceJob. CM TraceJob. CM TraceJob. CM TraceJob. CM TraceJob. pLMNTarget CM TraceJob. CM				
measurementPeriodUMTS collectionPerio dRrmUmts collectionPerio dRrmLte positioningMeth od CM measurementPeriodLectionPerio dRrmLte positioningMeth od CM measurementPeriodLectionPerio dRrmLte positioningMeth od CM TraceJob.collectionPerio dRrmLte positioningMeth od CO TraceJob.positioning measurement period collectionPeriod for M2, M3 in LTE within an Immediate MDT job. TraceJob.positioning measurement priodLectionPeriod within an Immediate MDT job. TraceJob.positioning measurement priodLectionPeriod for M2, M3 in LTE within an Immediate MDT job. TraceJob.positioning measurement priodLection period for M2, M3 in LTE within an Immediate MDT job. TraceJob.positioning measurement priodLection period for M2, M3 in LTE within an Immediate MDT job. TraceJob.measurement lt specifies the positioning method to be used for the Immediate MDT job. TraceJob.measurement lt specifies which measurement should be collected in an event triggered measurement collection. TraceJob.pLMNTarget TraceJob.pLMNTarget It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. TraceJob. Trac				
Immediate MDT job.		CM	TraceJob.	It specifies the measurement period for the Data Volume
CollectionPerio dRrmUmts eriodRrmUmts within an Immediate MDT job. CollectionPerio dRrmLte eriodRrmLte eriodRrmLte eriodRrmLte lt specifies the collection period for M2, M3 in LTE within an Immediate MDT job. CO TraceJob.collectionP lt specifies the collection period for M2, M3 in LTE within an Immediate MDT job. CO TraceJob.positioning lt specifies the positioning method to be used for the Immediate MDT job. CO TraceJob.measurement lt specifies which measurement should be collected in an event triggered measurement collection. CM TraceJob.pLMNTarget lt specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. CM TraceJob. It specifies MBSFN Area(s) for MBSFN MDT	measurementPeri		measurementPeriodUMT	
dRrmUmts eriodRrmUmts within an Immediate MDT job. CollectionPerio CM TraceJob.collectionP It specifies the collection period for M2, M3 in LTE within an Immediate MDT job. CO TraceJob.positioning It specifies the positioning method to be used for the Immediate MDT job. CO TraceJob.positioning It specifies which measurement should be collected in an event triggered measurement collection. CM TraceJob.pLMNTarget It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. CM TraceJob.				
CM TraceJob.collectionP lt specifies the collection period for M2, M3 in LTE within an Immediate MDT job. CO TraceJob.positioning lt specifies the positioning method to be used for the Immediate MDT job. TraceJob.measurement lt specifies which measurement should be collected in an event triggered measurement collection. CM TraceJob.pLMNTarget lt specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. TraceJob. It specifies MBSFN Area(s) for MBSFN MDT		CM		
dRrmLte eriodRrmLte an Immediate MDT job. CO TraceJob.positioning It specifies the positioning method to be used for the Immediate MDT job. TraceJob.measurement It specifies which measurement should be collected in an event triggered measurement collection. CM TraceJob.pLMNTarget It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. TraceJob. It specifies MBSFN Area(s) for MBSFN MDT		014		
positioningMeth od Method Immediate MDT job. measurementQuan tity CM TraceJob.pLMNTarget CM TraceJob.pLMNTarget CM TraceJob. TraceJob.pLMNTarget CM TraceJob. TraceJob.pLMNTarget CM TraceJob. TraceJob.pLMNTarget It specifies which measurement collection. It specifies which measurement collection. It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. It specifies MBSFN Area(s) for MBSFN MDT		CM		
od Method Immediate MDT job. measurementQuan tity CM TraceJob.measurement Quantity It specifies which measurement should be collected in an event triggered measurement collection. pLMNTarget CM TraceJob.pLMNTarget to be recorded uses as selected PLMN. mBSFNAreaList CM TraceJob. It specifies MBSFN Area(s) for MBSFN MDT		CO		
measurementQuan tity CM TraceJob.measurement It specifies which measurement should be collected in an event triggered measurement collection. CM TraceJob.pLMNTarget It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. mbsfnAreaList CM TraceJob. It specifies Mbsfn Area(s) for Mbsfn MDT				
tity Quantity event triggered measurement collection. pLMNTarget CM TraceJob.pLMNTarget It specifies which PLMN that the subscriber of the session to be recorded uses as selected PLMN. mBSFNAreaList CM TraceJob. It specifies MBSFN Area(s) for MBSFN MDT		CM		
pLMNTarget CM TraceJob.pLMNTarget It specifies which PLMN that the subscriber of the sessic to be recorded uses as selected PLMN. mBSFNAreaList CM TraceJob. It specifies MBSFN Area(s) for MBSFN MDT	tity	J.V.		
to be recorded uses as selected PLMN. mBSFNAreaList CM TraceJob. It specifies MBSFN Area(s) for MBSFN MDT	pLMNTarget	CM		It specifies which PLMN that the subscriber of the session
mBSFNAreaList CM TraceJob. It specifies MBSFN Area(s) for MBSFN MDT	_			to be recorded uses as selected PLMN.
mBSFNAreal ist measurement logging	mBSFNAreaList	CM		It specifies MBSFN Area(s) for MBSFN MDT
I Imparation Imparation of Imp			mBSFNAreaList	measurement logging.

6.3.3.4 Pre-condition

validTraceReference

Assertion Name	Definition
validTraceReference	The traceReference input parameter is valid, which means that the TraceIRP is aware of
	such TraceJob, which has this traceReference value and is aware of the
	ManagedEntity holding such Trace Session.

6.3.3.5 Post-condition

TraceSessionFound

Assertion Name	Definition
TraceSessionFound	The TraceIRP has found the requested TraceJob with the traceReference and can read
	the configured parameters.

6.3.3.6 Exceptions

Exception Name	Definition
notuniqueTraceReference	Condition: (validTraceReference) is false.
	Returned Information: output parameter status is set to "Failure".
	Exit state: Entry State.

6.3.3.7 Constraints

Name	Definition
traceCollectionEntityAddress CM,CO	Mandatory when tracing in EPS is supported;
qualifier	Mandatory when MDT is supported;
	Optional when tracing in UMTS is supported.
anonymizationOfMDTData	MDT is supported
areaScope	MDT is supported or RLF reporting is supported
listOfMeasurements	MDT is supported
reportingTrigger	MDT is supported
reportInterval	MDT is supported
reportAmount	MDT is supported
eventThreshold	MDT is supported
loggingInterval	MDT is supported
loggingDuration	MDT is supported
traceDepth	Trace is supported
triggeringEvent	Trace is supported
measurementPeriodLTE	MDT is supported
measurementPeriodUMTS	MDT is supported
collectionPeriodRrmUmts	MDT is supported

collectionPeriodRrmLte	MDT is supported
positioningMethod	MDT is supported
measurementQuantity	MDT is supported
pLMNTarget	Several PLMNs are supported in the RAN and a Managment Based Activation Trace Session is activated.
mBSFNAreaList	Logged MBSFN MDT is supported

6.3.4 Operation listActivatedTraceJobs (M)

6.3.4.1 Definition

This operation support IRPManager's request to list all the activated TraceJobs through Itf-N.

6.3.4.2 Input parameters

No input parameters for this operation.

6.3.4.3 Output parameters

Parameter Name	Qualifier	Matching Information	Comment
traceReferenceList			The TraceReferenceList provides the identification of
		TraceJob.traceRefe	each activated Trace Session.
		rence.objectinstan	If no TraceReference can be found, then this list is empty
		ce >	and status is "Success"
status	М	ENUM (Success,	The operation may fail because of a specified or an
		Failure)	unspecified reason.

6.3.5 Notification notifyTraceRecordingSessionFailure (O)

6.3.5.1 Definition

The TraceIRP notifies all subscribed IRPManagers and the Trace Collection Entity (if its address is provided) if a Trace Recording Session in a ManagedEntity has not been started due to any problem.

6.3.5.2 Input parameters

Parameter Name	Qualifiers	Matching Information	Comment
objectClass	M,Y	TraceIRP.objectClass	Notification header
objectInstance	M,Y	TraceIRP.objectInstance	Notification header
eventTime	M,Y		Notification header
notificationType	M,Y	"notifyTraceRecordingSessionFailure"	Notification header
systemDN	M,Y		Notification header
notificationID	O,Y		Notification header
traceRecordingSessionReference	O,N		The Trace Recording Session Reference may be visible only in signalling based activation.
traceReference	M,Y	TraceJob.traceReference	
reason	O,N		

6.3.5.3 Triggering event

6.3.5.3.1 From state

internalProblemInManagedEntity

Assertion Name	Definition
internalProblemInMa	Because of an internal problem the ManagedEntity cannot start a Trace Recording
nagedEntity	Session.

6.3.5.3.2 To state

newNotificationReported

Assertion Name	Definition
newNotificationRepo	The " notifyTraceRecordingSessionFailure " notification is emitted to the subscribed
rted	IRPManager(s).

6.3.6 Notification notifyTraceSessionLocalActivation (M)

6.3.6.1 Definition

The TraceIRP notifies all subscribed IRPManagers if a Trace Session is configured by the Element Manager.

6.3.6.2 Input parameters

Parameter Name	Qualifiers	Matching Information	Comment
objectClass	M,Y	1	Notification header
objectInstance	M,Y	TraceIRP.objectInstance	Notification header
eventTime	M,Y		Notification header
notificationType	M,Y	"notifyTraceSessionLocalActivation"	Notification header
systemDN	M,Y		Notification header
notificationID	O,Y		Notification header
traceReference	M,Y	TraceJob.traceReference	
traceTarget	M,Y	TraceJob.traceTarget	
iOCInstance	M,Y	ManagedEntity.objectInstance	

6.3.6.3 Triggering event

6.3.6.3.1 From state

unknownTraceReference

Assertion Name	Definition
unknownTraceReference	The TraceIRP has detected a traceReference associated to a Trace Session in a
	ManagedEntity that is not initiated via the ltf-N.

6.3.6.3.2 To state

newNotificationReported

Assertion Name	Definition
newNotificationReported	The " notifyTraceSessionLocalActivation " notification is emitted to the
	subscribed IRPManager(s).

6.3.7 Notification notifyTraceSessionIdentities (CM)

6.3.7.1 Definition

The ${\tt TraceIRP}$ or the MmeFunction notifies the Trace Collection Entity about the identities of the subscriber and Equipment in case of tracing a session in E-UTRAN only.

6.3.7.2 Input parameters

Parameter Name	Qualifiers	Matching Information	Comment
objectClass	M,Y	TraceIRP.objectClass, or	Notification
		MmeFunction.objectClass	header
objectInstance	M,Y	TraceIRP.objectInstance, or	Notification
		MmeFunction.objectClass	header
eventTime	M,Y		Notification
			header
notificationType	M,Y	"notifyTraceSessionIds"	Notification
			header
systemDN	M,Y		Notification
			header
notificationID	O,Y		Notification
			header
traceReference	M,Y	TraceJob.traceReference	
traceRecordingSessionReference	M,Y	TraceJob.traceRecordingSessionReference	
traceTarget	M,Y	TraceJob.traceTarget	

6.3.7.3 Triggering event

6.3.7.3.1 From state

FFS

Assertion Name	Definition
FFS	FFS

6.3.7.3.2 To state

FFS

Assertion Name	Definition
FFS	FFS

6.3.7.4 Constraint

Name	Definition
notifyTraceSessionIdentities Notification CM qualifier	Tracing is performed only in E-UTRAN

Annex A (informative): Change history

	Change history									
Date	TSG #	TSG Doc.	CR	Rev	Subject/Comment	Cat	Old	New		
Apr 2007	S5_52	S5-070445			Submitted by SA5 prior SA#36 for Information with the intention to get SA#36 Rel-7 Approval for this TS and the CORBA Solution Set TS 32.443		1.0.0			
Jun 2007		SP-070288			Submitted to SA#36 for Approval		1.0.0	7.0.0		
Mar 2008		SP-080058			Standardize the DN id of UTRAN cell as the identification for the trace target in case of cell traffic trace	F	7.0.0	7.1.0		
Dec 2008	SP-42	SP-080846	0002		Introducing EPS in Subscriber and Equipment Trace	С	7.1.0	8.0.0		
Dec 2009					Upgrade to Release 9		8.0.0	9.0.0		
Jan 2010					Removal of track changes and correction of change history		9.0.0	9.0.1		
Dec 2010	SP-50	SP-100833	003	1	Correcting the Identification of IMS Subscriber Tracing - Align with 32.421	F	9.0.1	10.0.0		
Mar 2011		SP-110102		-	Adding Minimization of Drive Tests (MDT) to Trace IRP	В	10.0.0	10.1.0		
		SP-110292		1	Add areascope parameter as a MDT configuration	F	10.1.0	10.2.0		
May 2011	SP-52	SP-110286	800	1	Modify the defintion of traceTarget	С	10.2.0	11.0.0		
Dec 2011	SP-54	SP-110716	013	1	Add RLF reporting configuration -Align with 32.422	В	11.0.0	11.1.0		
Dec 2011	SP-54	SP-110715	015	2	Support multiple cells in area based MDT	Α	11.0.0	11.1.0		
Dec 2011	SP-54	SP-110715	017	2	Add TCE address for UTRAN MDT activation		11.0.0	11.1.0		
March 2012	SP-55	SP-120053	020	1	Inconsistency correction on trace target -Align with 32.422		11.1.0	11.2.0		
June- 2012	SP-56	SP-120368	0215		Alignment of the Anonymization parameter with TS 32.422		11.2.0	11.3.0		
Sep-2012	SP-57	SP-120571	0216	1	Adding new MDT configuration parameters to align with TS 37.320 and TS 32.422		11.3.0	11.4.0		
Sep-2012	SP-57	SP-120571	0219	1	Add missing threshold parameter for UMTS event triggered measurements		11.3.0	11.4.0		
		SP-120795	0217	2	Add RCEF reporting	В				
		SP-120795	0222	3	Correction on scope, references and abreviations	F	Ť			
		SP-120794	0226	1	Correction of UMTS M2 reporting trigger configuration -Align with 32.422	Α	Ī			
Dec-2012	SP-58	SP-120796	0227	1	Introducing common MDT measurement period attribute in Trace IRP	В	11.4.0	11.5.0		
		SP-120796	0228	1	Addition of Network Sharing	С	i i			
		SP-120795		1	Add measurement M7	В	1			
		SP-120795		-	Combine measurement period parameters for LTE	С	Ť			
Mar-2013	SP-59	SP-130057	0231	1	Editorial corrections in 32.442		11.5.0	11.6.0		
		SP-140558		-	Addition of missing parameters relating to RCEF	F	11.6.0	11.7.0		
Oct 2014					Automatic upgrade (MCC)		11.7.0	12.0.0		
Dec 2014	SP-66	SP-140800	0237	-	Clarify the Trace Reference for shared networks	В	12.0.0	12.1.0		
Jun 2015		SP-150315		2	Multi-Broadcast Single Frequency Network (MBSFN) Minimization of Drive Tests (MDT) enhancement.	В	12.1.0	13.0.0		

	Change history								
Date	Meeting	Tdoc	CR	Rev	Cat	Subject/Comment	New version		
2016-12						Correction of LTE logo (MCC)	13.0.1		
2017-04	SA#75	-	-	-		Promotion to Release 14 without technical change	14.0.0		
2018-06	-	-	-	-	-	Update to Rel-15 version (MCC)	15.0.0		
2020-07	-	-	=	-	-	Update to Rel-16 version (MCC)	16.0.0		
2022-04	-	-	-	-	-	Update to Rel-17 version (MCC)	17.0.0		
2024-04	-	-	-	-	-	Update to Rel-18 version (MCC)	18.0.0		
2025-09	SA#109	-	-	-	-	Update to Rel-19 version (MCC)	19.0.0		

History

Document history						
V19.0.0	October 2025	Publication				