# ETSI TS 132 511 V17.1.0 (2022-07)



Universal Mobile Telecommunications System (UMTS); LTE; Telecommunication management; Automatic Neighbour Relation (ANR) management; Concepts and requirements (3GPP TS 32.511 version 17.1.0 Release 17)



Reference RTS/TSGS-0532511vh10

Keywords

LTE,UMTS

#### **ETSI**

650 Route des Lucioles F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - APE 7112B Association à but non lucratif enregistrée à la Sous-Préfecture de Grasse (06) N° w061004871

#### Important notice

The present document can be downloaded from: <u>http://www.etsi.org/standards-search</u>

The present document may be made available in electronic versions and/or in print. The content of any electronic and/or print versions of the present document shall not be modified without the prior written authorization of ETSI. In case of any existing or perceived difference in contents between such versions and/or in print, the prevailing version of an ETSI deliverable is the one made publicly available in PDF format at <a href="http://www.etsi.org/deliver">www.etsi.org/deliver</a>.

Users of the present document should be aware that the document may be subject to revision or change of status. Information on the current status of this and other ETSI documents is available at <u>https://portal.etsi.org/TB/ETSIDeliverableStatus.aspx</u>

If you find errors in the present document, please send your comment to one of the following services: <u>https://portal.etsi.org/People/CommiteeSupportStaff.aspx</u>

If you find a security vulnerability in the present document, please report it through our Coordinated Vulnerability Disclosure Program: https://www.etsi.org/standards/coordinated-vulnerability-disclosure

#### Notice of disclaimer & limitation of liability

The information provided in the present deliverable is directed solely to professionals who have the appropriate degree of experience to understand and interpret its content in accordance with generally accepted engineering or other professional standard and applicable regulations.

No recommendation as to products and services or vendors is made or should be implied.

No representation or warranty is made that this deliverable is technically accurate or sufficient or conforms to any law and/or governmental rule and/or regulation and further, no representation or warranty is made of merchantability or fitness for any particular purpose or against infringement of intellectual property rights.

In no event shall ETSI be held liable for loss of profits or any other incidental or consequential damages.

Any software contained in this deliverable is provided "AS IS" with no warranties, express or implied, including but not limited to, the warranties of merchantability, fitness for a particular purpose and non-infringement of intellectual property rights and ETSI shall not be held liable in any event for any damages whatsoever (including, without limitation, damages for loss of profits, business interruption, loss of information, or any other pecuniary loss) arising out of or related to the use of or inability to use the software.

#### Copyright Notification

No part may be reproduced or utilized in any form or by any means, electronic or mechanical, including photocopying and microfilm except as authorized by written permission of ETSI.

The content of the PDF version shall not be modified without the written authorization of ETSI. The copyright and the foregoing restriction extend to reproduction in all media.

> © ETSI 2022. All rights reserved.

### Intellectual Property Rights

#### **Essential patents**

IPRs essential or potentially essential to normative deliverables may have been declared to ETSI. The declarations pertaining to these essential IPRs, if any, are publicly available for **ETSI members and non-members**, and can be found in ETSI SR 000 314: "Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards", which is available from the ETSI Secretariat. Latest updates are available on the ETSI Web server (https://ipr.etsi.org/).

Pursuant to the ETSI Directives including the ETSI IPR Policy, no investigation regarding the essentiality of IPRs, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

#### Trademarks

The present document may include trademarks and/or tradenames which are asserted and/or registered by their owners. ETSI claims no ownership of these except for any which are indicated as being the property of ETSI, and conveys no right to use or reproduce any trademark and/or tradename. Mention of those trademarks in the present document does not constitute an endorsement by ETSI of products, services or organizations associated with those trademarks.

**DECT<sup>TM</sup>**, **PLUGTESTS<sup>TM</sup>**, **UMTS<sup>TM</sup>** and the ETSI logo are trademarks of ETSI registered for the benefit of its Members. **3GPP<sup>TM</sup>** and **LTE<sup>TM</sup>** are trademarks of ETSI registered for the benefit of its Members and of the 3GPP Organizational Partners. **oneM2M<sup>TM</sup>** logo is a trademark of ETSI registered for the benefit of its Members and of the oneM2M Partners. **GSM**<sup>®</sup> and the GSM logo are trademarks registered and owned by the GSM Association.

### Legal Notice

This Technical Specification (TS) has been produced by ETSI 3rd Generation Partnership Project (3GPP).

The present document may refer to technical specifications or reports using their 3GPP identities. These shall be interpreted as being references to the corresponding ETSI deliverables.

The cross reference between 3GPP and ETSI identities can be found under http://webapp.etsi.org/key/queryform.asp.

### Modal verbs terminology

In the present document "shall", "shall not", "should", "should not", "may", "need not", "will", "will not", "can" and "cannot" are to be interpreted as described in clause 3.2 of the <u>ETSI Drafting Rules</u> (Verbal forms for the expression of provisions).

"must" and "must not" are NOT allowed in ETSI deliverables except when used in direct citation.

## Contents

Intelle	ectual Property Rights	2
Legal	Notice	2
Moda	l verbs terminology	2
Forew	vord	4
Introd	luction	4
1	Scope	5
2	References	
3	Definitions and abbreviations	
3.1	Definitions	
3.2	Abbreviations	
4	Concepts and background	6
5	Requirements	6
5.1	Business level requirements	
5.1.1	Void	
5.1.1.1	Void	7
5.1.1.2	2 Void	7
5.1.1.3	3 Void	7
5.2	Specification level requirements	7
5.2.1	Void	7
5.2.2	Void	7
5.2.3	Void	7
5.2.4	Use cases	7
5.2.4.1	Management of fully automatic ANR function	7
5.2.4.2	2 Manual start of the ANR function by operator	8
5.2.4.3	B Handling of noX2 attribute	8
5.2.4.4	4 Manual stop of the ANR function by operator	9
5.2.5	Requirements	
5.2.5.1		
5.2.5.2		
5.2.5.3	ANR function management for NG-RAN	12
Anne	x A (informative): Change history	13
Histor	ry	14

3

### Foreword

This Technical Specification has been produced by the 3<sup>rd</sup> Generation Partnership Project (3GPP).

The contents of the present document are subject to continuing work within the TSG and may change following formal TSG approval. Should the TSG modify the contents of the present document, it will be re-released by the TSG with an identifying change of release date and an increase in version number as follows:

Version x.y.z

where:

- x the first digit:
  - 1 presented to TSG for information;
  - 2 presented to TSG for approval;
  - 3 or greater indicates TSG approved document under change control.
- y the second digit is incremented for all changes of substance, i.e. technical enhancements, corrections, updates, etc.
- z the third digit is incremented when editorial only changes have been incorporated in the document.

### Introduction

The present document is part of a TS-family covering the 3<sup>rd</sup> Generation Partnership Project Technical Specification Group Services and System Aspects, Telecommunication management; as identified below:

32.511: "Automatic Neighbour Relation (ANR) management; Concepts and requirements".

### 1 Scope

The present document describes the concepts and requirements for the management of Automatic Neighbour Relation (ANR) in UTRAN and E-UTRAN across the Itf-N. The ANR management is a key feature of Self Organizing Networks (SON) [4].

The NCR concept and background information are described in clause 4. The requirements for management of NCR are defined in clause 5.

### 2 References

The following documents contain provisions which, through reference in this text, constitute provisions of the present document.

- References are either specific (identified by date of publication, edition number, version number, etc.) or non-specific.
- For a specific reference, subsequent revisions do not apply.
- For a non-specific reference, the latest version applies. In the case of a reference to a 3GPP document (including a GSM document), a non-specific reference implicitly refers to the latest version of that document *in the same Release as the present document*.
- [1] 3GPP TR 21.905: "Vocabulary for 3GPP Specifications".
- [2] 3GPP TS 32.101: "Telecommunication management; Principles and high level requirements".
- [3] 3GPP TS 32.102: "Telecommunication management; Architecture".
- [4] 3GPP TR 32.816: "Telecommunication management; Study on Management of Evolved Universal Terrestrial Radio Access Network (E-UTRAN) and Evolved Packet Core (EPC)".
- [5] 3GPP TS 32.501 "Telecommunication management; Self-Configuration of Network Elements; Concepts and requirements".
- [6] 3GPP TS 36.300 "Evolved Universal Terrestrial Radio Access (E-UTRA) and Evolved Universal Terrestrial Radio Access Network (E-UTRAN); Overall description; Stage 2".
- [7] 3GPP TS 32.301 "Telecommunication management; Configuration Management (CM); Notification Integration Reference Point (IRP); Requirements".
- [8] 3GPP TS 25.484 "Automatic Neighbour Relation (ANR) for UTRAN; Stage 2".

### 3 Definitions and abbreviations

For the purposes of the present document, the terms and definitions given in TS 32.101 [2], TS 32.102 [3] and TS 21.905 [1] and the following apply. A term defined in the present document takes precedence over the definition of the same term, if any, in TS 32.101 [2], TS 32.102 [3] and TS 21.905 [1], in that order.

### 3.1 Definitions

For the purposes of the present document, the terms and definitions given in TR 21.905 [1] and the following apply. A term defined in the present document takes precedence over the definition of the same term, if any, in TR 21.905 [1].

**ANR function:** The ANR function in E-UTRAN is described in TS 36.300 [6], section 22.3.2a. The ANR function in UTRAN is described in TS 25.484 [8].

**Neighbour Cell Relation:** The Neighbour Cell Relation (NCR) in E-UTRAN is defined in TS 36.300 [6] section 22.3.2a. The Neighbour Cell Relation in UTRAN is defined in TS 25.484 [8].

Searchlist: List of frequencies and supporting information to be used for neighbour cell measurements. The Searchlist contains entries for E-UTRAN and supported IRATs.

### 3.2 Abbreviations

For the purposes of the present document, the abbreviations given in TR 21.905 [1] and the following apply. An abbreviation defined in the present document takes precedence over the definition of the same abbreviation, if any, in TR 21.905 [1].

ANR	Automatic Neighbour Relation
eNB	eNodeB or evolved NodeB
NCR	Neighbour Cell Relation
NCRT	Neighbour Cell Relation Table
UC	Use Case

### 4 Concepts and background

For E-UTRAN, the ANR function in the eNB relates to the Use Cases **Establishment of new eNB in network** and **Optimisation of the neighbourhood list** in [4].

- For **Establishment of new eNB in network.** If the operator so chooses, the OAM system adds and configures NCRs before the eNB goes into operation.
- For **Optimisation of the neighbourhood list**, the ANR function deals with automatic NCR additions and removals. It minimizes the need for planning and configuring NCRs. If the operator so chooses, the OAM system adds and configures NCRs or removes NCRs after the eNB goes into operation.

For UTRAN, the ANR function concept and overall description is documented in TS 25.484 [8].

- The ANR function in RNC allows OAM system to manage the NCRT. OAM system can add and delete NCRs and also change the attributes of the NCRs. The OAM system is informed about changes in the NCRT made by ANR function.

### 5 Requirements

### 5.1 Business level requirements

**REQ-ANR-CON-001** NCRs shall be set up and optimized with no or minimal human intervention.

**REQ-ANR-CON-002** For E-UTRAN, initial status of the newly created NCR by ANR function shall be such that HO is allowed, X2 connection setup is allowed, and the NCR is allowed to be removed by ANR function in eNB.

**REQ-ANR-CON-003** E-UTRAN ANR supports management of NCRs from E-UTRAN to E-UTRAN, from E-UTRAN to UTRAN, from E-UTRAN to CDMA2000, from E-UTRAN to GERAN and from E-UTRAN to NG-RAN.

**REQ-ANR-CON-004** For UTRAN, initial status of the newly created NCR by ANR function shall be such that HO is allowed and the NCR is allowed to be removed by ANR function in RNC.

**REQ-ANR-CON-005** UTRAN ANR supports management of NCRs from UTRAN to UTRAN, from UTRAN to E-UTRAN and from UTRAN to GERAN.

- 5.1.1 Void
- 5.1.1.1 Void
- 5.1.1.2 Void
- 5.1.1.3 Void
- 5.2 Specification level requirements
- 5.2.1 Void
- 5.2.2 Void
- 5.2.3 Void
- 5.2.4 Use cases

### 5.2.4.1 Management of fully automatic ANR function

Use Case Stage	Evolution / Specification					
Goal (*)	<b>Goal (*)</b> The goal is that the IRPManager may add and remove NCRs and that it may change attributes of the NCRs					
Actors and Roles (*)	- IRPManager as user					
Telecom resources	ANR function     eNB or RNC					
Assumptions						
Pre conditions	Pre conditions       - The ANR function in eNB or RNC is active;         - The cell may or may not have Neighbour Cell Relations configured by O&M         - For E-UTRAN, the eNB has finished Use Case Self-configuration of a new eNodeB [5];         - For UTRAN, the RNC is properly installed and running.					
Begins when	Begins when This Use Case begins when all pre conditions have been met.					
Step 1 (*) (M)	<ul> <li>If the IRPManager finds out that an unsuitable Neighbour Cell Relation has been added by ANR, the IRPManager may "block" that particular Neighbour Cell Relation in the Blocklist.</li> <li>If the IRPManager finds out that a desired Neighbour Cell Relation has not been added by ANR, the IRPManager may "allow" that particular Neighbour Cell Relation in the Allowlist.</li> <li>The IRPManager may uncheck the noRemove attribute from any present Neighbour Cell Relation.</li> </ul>					
Ends when (*)	This Use Case ends when the eNB or RNC is taken out of service or when the ANR function is stopped.					
Exceptions	<b>xceptions</b> One of the steps identified above fails and retry is unsuccessful.					
Post Conditions						
Traceability (*)	REQ-ANR-CON-001					

Use Case Stage	ge Evolution / Specification					
Goal (*)	The ANR function in eNB or RNC can be enabled by IRPManager.					
Actors and Roles (*)	- IRPManager as user					
Telecom resources	- ANR function - eNB or RNC					
Assumptions	Assumptions					
Pre conditions	<ul> <li>The ANR function is not active;</li> <li>The eNB or RNC may have Neighbour Cell Relations. The NCRs may be configured by O&amp;M or be may have been added by ANR function if ANR function has been active previously.</li> </ul>					
Begins when	Begins when         The Use Case begins when the IRP Manager starts the ANR function.					
Step 1 (*) (M)	The IRPManager enables the ANR function in eNB or RNC.					
Ends when (*)	Ends when all steps identified above are completed or when an exception occurs					
Exceptions	One of the steps identified above fails and retry is unsuccessful.					
Post Conditions						
Traceability (*)						

### 5.2.4.2 Manual start of the ANR function by operator

### 5.2.4.3 Handling of noX2 attribute

#### Use Case 1

IRPManager needs to be able to forbid and allow the establishment of X2 interfaces from the source macro eNBs to a target eNB. IRPManager is aware that the target eNB cannot support X2 connections. This UC on how noX2 is used relates to node level rather than cell level.

#### Use Case 2

IRPManager needs to be able to allow and forbid the establishment of X2 interfaces from the source HeNBs to a target macro eNB. This UC supports the case when a potentially large number of HeNBs in the vicinity of a macro eNB, X2 establishment requests from HeNB might saturate the physical ports of the macro eNB (not in terms of bandwidth saturation but rather the saturation in terms of the number of simultaneous establishment requests supported). This UC on how noX2 is used relates to node level rather than Cell level.

#### Use Case 3

IRPManager needs to be able to forbid the establishment of the X2 interface from (IRPManager's) operator's eNB to another operator's eNB or to an eNB that belongs to another unwanted PLMN. This UC supports the case when the IP address of the target eNB cannot be obtained or the X2 handovers to another unwanted PLMN are not allowed. This UC on how noX2 is used relates to node level rather than cell level.

#### Use Case 4

IRPManager needs to be able to ask for the release of the X2 interface improperly established by eNB. This UC supports the case when the serving eNB has established an X2 interface (e.g., by ANR) before IRPManager had a chance to forbid the establishment of that X2 interface. The IRPManager needs to be able to ask the serving eNB to release the X2 interface to the target eNB. This UC on how noX2 is used relates to node level rather than cell level.

Use Case Stage	Case Stage Evolution / Specification				
Goal (*)	The ANR function in eNB or RNC can be disabled by IRPManager.				
Actors and Roles (*)	- IRPManager as user				
Telecom resources					
Assumptions					
Pre conditions	- The ANR function is active				
Begins when	The Use Case begins when the IRPManager makes a decision to disable the ANR function.				
Step 1 (*) (M)	The IRPManager disables the ANR function in eNB or RNC.				
Ends when (*)	Ends when all steps identified above are completed or when an exception occurs.				
Exceptions	One of the steps identified above fails and retry is unsuccessful.				
Post Conditions	The ANR function in eNB or RNC is disabled by IRPManager successfully or unsuccessfully. All existing NCRs, whether created by ANR or otherwise are unaltered.				
Traceability (*)	REQ-ANR-FUN-10, REQ-ANR-FUN-26				

### 5.2.4.4 Manual stop of the ANR function by operator

### 5.2.5 Requirements

#### 5.2.5.1 ANR function management in E-UTRAN

The business level requirements in section 5.1 are decomposed into the following specification level requirements, applicable for E-UTRAN:

REQ-ANR-FUN-01 An IRPManager shall be able to request that HO be allowed from source cell to target cell.

- REQ-ANR-FUN-02 An IRPManager shall be able to request that HO be prohibited from source cell to target cell.
- **REQ-ANR-FUN-03** An IRPManager shall be able to request that HO be allowed from source cell to target cell and that no other entity than an IRPManager can remove that request. This is termed as HO allow-listing.
- **REQ-ANR-FUN-04** An IRPManager shall be able to request that HO be prohibited from source cell to target cell and that no other entity than an IRPManager can remove that request. This is termed as HO block-listing.
- **REQ-ANR-FUN-05** An IRPAgent shall inform the IRPManager about success or failure of IRPManager operations to allow HO, prohibit HO, HO allow-list and HO block-list.
- **REQ\_ANR-FUN-06** An IRPManager shall be able to request establishment of an X2 connection from one eNB to another eNB.
- REQ-ANR-FUN-07 An IRPManager shall be able to request the release of an X2 connection between two eNBs.
- **REQ-ANR-FUN-08** An IRPManager shall be able to request that X2 interface from one eNB to another eNB be established if the X2 interface is not established and that the release of X2 interface be prohibited. No other entity than an IRPManager can remove that request. This is termed as X2 allow-listing.
- **REQ-ANR-FUN-09** An IRPManager shall be able to request that X2 interface from one eNB to another eNB be released if the X2 interface is established and that the establishment of the X2 interface be prohibited. No other entity than an IRPManager can remove that request. This is termed as X2 block-listing.
- **REQ-ANR-FUN-10** Operator shall be able to disable/enable one eNB or multiple eNB's ANR function when needed.

#### REQ-ANR-FUN-11 void

- **REQ-ANR-FUN-12** An IRPManager shall be able to add and configure new NCRs in the eNB.
- REQ-ANR-FUN-13 An IRPManager shall be able to remove NCRs in the eNB
- **REQ-ANR-FUN-14** An IRPAgent shall inform the IRPManager about changes to the NCR according to TS 32.301 [7].
- **REQ-ANR-FUN-15** A Searchlist is needed for each cell. The IRPManager should be able to configure the Searchlist.
- **REQ-ANR-FUN-16** An IRPAgent shall inform the IRPManager about the newly added and removed NCRs according to TS 32.301 [7].
- REQ-ANR-FUN-17 An IRPManager shall be able to retrieve ANR related attribute values on cell level, identifying:
  - Source cell & target cell;
  - NCR status (locked, unlocked);
  - HO status (allowed, prohibited).

The "locked" NCR status indicates that the NCR shall not be removed by the ANR function.

The "unlocked" NCR status indicates that the NCR may be removed by the ANR function.

The "allowed" HO status indicates that handovers are allowed for this NCR.

The "prohibited" HO status indicates that handovers are prohibited for this NCR.

The combination of "locked" NCR status and "allowed" HO status is a "allowlisted" relation.

The combination of "locked" NCR status and "prohibited" HO status is a "blocklisted" relation.

- **REQ-ANR-FUN-18** The IRPAgent shall support a capability allowing the IRPManager to determine whether the X2 interface between two eNodeBs is established or not established.
- **REQ-ANR-FUN-19** IRPManager shall be able to request that the source eNB be prohibited to use X2 interface for HOs to a target eNB even if the X2 interface exists between the eNBs. No other entity than an IRPManager can remove that request. This is termed as X2HO block-listing.
- **REQ-ANR-FUN-20** The IRPAgent shall support a capability allowing the IRPManager to retrieve the X2 allowlisted and blocklisted eNBs.

#### 5.2.5.2 ANR function management in UTRAN

The business level requirements in section 5.1 are decomposed into the following specification level requirements, applicable for UTRAN:

- **REQ-ANR -FUN-21** The IRPAgent shall support a capability allowing the IRPManager to request that HO be allowed from source cell to target cell.
- **REQ-ANR-FUN-22** The IRPAgent shall support a capability allowing the IRPManager to request that HO be prohibited from source cell to target cell.
- **REQ-ANR-FUN-23** The IRPAgent shall support a capability allowing the IRPManager to request that HO be allowed from source cell to target cell and that no other entity than an IRPManager can remove that request. This is termed as HO allow-listing.
- **REQ-ANR-FUN-24** The IRPAgent shall support a capability allowing the IRPManager to request that HO be prohibited from source cell to target cell and that no other entity than an IRPManager can remove that request. This is termed as HO block-listing.
- **REQ-ANR-FUN-25** The IRPAgent shall inform the IRPManager about success or failure of IRPManager operations to allow HO, prohibit HO, HO allow-list and HO block-list.
- **REQ-ANR-FUN-26** The IRPAgent shall support a capability allowing the IRPManager to disable/enable ANR function in RNC when needed.
- **REQ-ANR-FUN-27** The IRPAgent shall support a capability allowing the IRPManager to add and configure new NCRs in the RNC.
- **REQ-ANR-FUN-28** The IRPAgent shall support a capability allowing the IRPManager to remove NCRs in the RNC.
- **REQ-ANR-FUN-29** The IRPAgent shall inform the IRPManager about changes to the NCR according to TS 32.301 [7].
- **REQ-ANR-FUN-30** The IRPAgent shall inform the IRPManager about the newly added and removed NCRs according to TS 32.301 [7].
- **REQ-ANR-FUN-31** The IRPAgent shall support a capability allowing the IRPManager to retrieve ANR related attribute values on cell level, identifying:
  - Source cell & target cell
  - NCR status (locked, unlocked)
  - HO status (allowed, prohibited)

The "locked" NCR status indicates that the NCR shall not be removed by the ANR function.

The "unlocked" NCR status indicates that the NCR may be removed by the ANR function.

The "allowed" HO status indicates that handovers are allowed for this NCR.

The "prohibited" HO status indicates that handovers are prohibited for this NCR.

The combination of "locked" NCR status and "allowed" HO status is a "allowisted" relation.

The combination of "locked" NCR status and "prohibited" HO status is a "blocklisted" relation.

### 5.2.5.3 ANR function management for NG-RAN

The business level requirements in section 5.1 are decomposed into the following specification level requirements, applicable for NG-RAN:

- **REQ-ANR -FUN-x1 The IRPAgent shall support a capability allowing the IRPManager to** request that HO is allowed from source E-UTRAN cell to target NG-RAN cell.
- **REQ-ANR-FUN-x2** The IRPAgent shall support a capability allowing the IRPManager to request that HO is prohibited from source E-UTRAN cell to target NG-RAN cell.
- **REQ-ANR-FUN-x3 The IRPAgent shall support a capability allowing the IRPManager to** request that HO is allowed from source E-UTRAN cell to target NG-RAN cell and that no other entity than an IRPAgent can remove that request. This is termed as HO allow-listing.
- **REQ-ANR-FUN-x4 The IRPAgent shall support a capability allowing the IRPManager to** request that HO is prohibited from source E-UTRAN cell to target NG-RAN cell and that no other entity than an IRPAgent can remove that request. This is termed as HO block-listing.

# Annex A (informative): Change history

	Change history						
Date	Meeting	TDoc	CR	Rev	Cat	Subject/Comment	New version
2008-12						Submitted to SA#42 for information and approval	8.0.0
2009-03	SP-43	SP-090213	001	1		Remove solution related terms and inconsistencies in Requirement specification and add clarifications	8.1.0
2009-06	SP-44	SP-090290	002			Clarify requirement REQ-ANR-FUN-18	8.2.0
2009-12	-	-	-	-		Update to Rel-9 version (MCC)	9.0.0
2011-03	-	-	-	-		Update to Rel-10 version (MCC)	10.0.0
2011-06	SP-52	SP-110293	009	1		Introducing ANR use cases for UTRAN	11.0.0
2011-09	SP-53	SP-110540	010			Introducing ANR concepts and requirements for UTRAN	11.1.0
2012-09	SP-57	SP-120574	011			Clean-up changes for ANR management concepts and requirements	11.2.0
2014-10	-	-	-	-		Update to Rel-12 version (MCC)	12.0.0
2016-01	-	-	-	-		Update to Rel-13 version (MCC)	13.0.0
2017-04	SA#75	-	-	-		Promotion to Release 14 without technical change	14.0.0
2018-01	SA#78	SP-170972	0018	1	Α	Alignment with RAN specification	14.1.0
2018-03	SA#79	SP-180070	0025	-	Α	Converting Editor's Note to normative text.	14.2.0
2018-06	-	-	-	-	-	Update to Rel-15 version (MCC)	15.0.0
2019-12	SA#86	SP-191180	0026	-	В	E-UTRAN ANR Specification level requirements for NR support	16.0.0
2022-04	-	-	-	-	-	Update to Rel-17 version (MCC)	17.0.0
2022-06	SA#96	SP-220593	0027	-	F	Correcting non inclusive language	17.1.0

# History

Document history					
V17.0.0	April 2022	Publication			
V17.1.0	July 2022	Publication			